

Scholastic ***HYPERSCREEN***TM

**NEW "HYPERMEDIA POWER"
FOR APPLE II AND MS-DOS
PERSONAL COMPUTERS!**

**Compatible with
Scholastic
Graphics & Sound
Booster Packs!**

No program loads more multimedia potential into your classroom computer than Scholastic HyperScreen. You create "stacks" of screens linked by on-screen "hot-spots" for branching interactive lessons and presentations. Includes fonts, graphics, sounds, drawing tools and unique "hot spot" transitions.

by George Brackett

 **SCHOLASTIC**

Apple

Apple® IIe (128K), IIc,
IIc Plus, or IIGS
Optional: Mouse, Joystick, Printer

Scanned by cvxmelody

<http://www.cvxmelody.net/AppleUsersGroupSydneyAppleIIDiskCollection.htm>

Scholastic

HYPERSCREEN



Scholastic

TEACHER EDITION
ISBN: 0-590-83724-9

SCHOLASTIC HYPERSCREEN™ 2.0 ADDENDUM

Scholastic HyperScreen 2.0, the expanded version of *Scholastic HyperScreen*, includes exciting new features that enhance your presentations and make stack creation easier than ever before:

- New button types offer synthesized speech and scoring.
- New options to sound a bell tone or highlight a button give all buttons enhanced capabilities.
- New browsing features offer increased browsing ease for all users.
- New editing features speed the creation of screens and stacks.

New Button Types

Say Text Button

With the proper speech synthesizer attached, you can create a button that "speaks" any text you enter.

NOTE: Use of this button type requires an Echo™ II, Echo IIb, or Cricket™ speech synthesizer as part of your computer set-up.

To create a Say Text button, follow the instructions below:

1. When choosing a button type, select Say Text from the Button Type menu. (See page 57 of the Reference Guide for more information on choosing a button type.)
2. Enter the text to be spoken in the text box which appears in the same way you enter pop-up text. (See page 64 for further information on entering text for a Pop-up Text button.)
3. If you choose the Visible option, your entered text will be displayed in a window as it is spoken. It will remain on screen until the user clicks a button or presses a key.

NOTE: You may want to choose the Visible option only if the written text you use is spelled correctly—in other words, you haven't used phonetic spelling to achieve correct pronunciation.

When the button is clicked (or activated as part of a Multi-button sequence), the speech synthesizer speaks the text using robotic speech. If the computer is not equipped with a compatible synthesizer, nothing happens.

SPEECH SYNTHESIZER PRONUNCIATION

If you have not previously used a speech synthesizer, experiment with the following methods to improve the sound of the spoken text:

- **Creative Spelling** It may be necessary to use some creative spelling to achieve the right sounds. For example, the synthesizer will pronounce "pilot" as "pillot." Spelling the word as "pielot" corrects the pronunciation.

- **Phonetics and Echo Commands** A more difficult but accurate method to achieve correct pronunciation is to embed phonetics and additional Echo commands directly in your text. To send phonetic codes, surround them with the curly brackets { and }. For example, {H>I3P<RSCR<&N} causes the synthesizer to say "HyperScreen" quite clearly, much better than it would say the text of the name itself. To send additional Echo commands, surround them with the square brackets [and]. For example, including [40P] in the text raises the pitch of all subsequent speech above its normal level of 22. The Echo Command Reference Charts at the end of this addendum summarize the phoneme codes and the additional Echo commands. For more information and examples, see the manual supplied with your speech synthesizer.

SAY TEXT STACK DISKS

To use the Say Text button, it must be part of a stack located on a special Stack disk created by *HyperScreen* version 2.0 or above. To create a Stack disk with speech capability:

1. Select Create Stack Disk from the APPLE MENU as usual.
2. After the disk is formatted, you will see the prompt "OK to install Echo speech capability? (Uses extra 10K)." Click OK or press Return. The necessary software to create a disk capable of speech will be added to your Stack disk.
3. If you don't plan to use the Say Text button in your stacks, click Cancel or press Esc to save the space that would be taken up by the Echo software.

ADDITIONAL NOTES ON THE SAY TEXT BUTTON

- **Occasional Delays** When using *HyperScreen*, memory limitations sometimes require loading the text-to-speech software before speech can be heard. The program does this automatically when necessary. As the software is automatically loaded, you may notice some hesitation in opening a screen, hearing the speech after creating a Say Text button, or browsing a stack containing Say Text buttons. If you browse from a self-booting Stack disk, however, there will be no extra delays.
- **Using Say Text with Sound/FX Buttons** Because of memory limitations, only one type of button, either Say Text or Sound/FX, but not both, can be contained on an individual screen. Up to 15 Say Text buttons, each with different text, can be included on a single screen.

Score Button

With the Score button, you can accumulate and report a score as your user moves through the stack. The report appears in a pop-up window on your screen. For instance, you could create a stack with a series of questions and provide feedback on how well your users answered. To create a Score button, select this type from the Button Type menu. (See page 57 for further information on this menu.) Then choose the scoring method the button will use. From the Button Info box, select one of four possible Actions:

- **Zero** Activating a Score Zero button sets the score and the number of tries to zero. Use this button type at the beginning of any series of assessment questions.
- **Right** Activating a Score Right button increases both the score and the number of tries by one.

- **Wrong** Activating a Score Wrong button increases the number of tries by one; the score remains the same.
- **Report** Activating a Score Report button pops up a window listing the current values of the score and the number of tries.

One way to use the Score button is to create a screen with multiple choices for the user to select. The Score button can be included as part of a Multi-button list, so that when the user selects a correct answer, the score is increased and the user receives a congratulatory pop-up text message or is linked to another screen. A Score button can also be included in a Multi-button list so that when the user selects an incorrect answer, the score is not increased, the number of tries increases, and the user receives a pop-up hint or is linked to another screen.

Another way to use the Score button is to create a Text Entry button where the correct and incorrect responses link the user to Multi-buttons on the screen. Score buttons can be included in the Multi-button list for the user's correct or incorrect responses, and Pop-up Text and Link to Screen buttons can be created to give appropriate feedback to the user.

Enhanced Button Options

Bell and Hilite Button Options

Two new options have been added for any button, in addition to the original Clickable and Do On Opening options in the Button Info box. (For more information on using the Button Info box, see page 54.)

If you select the Bell option, the computer's bell will sound when the button is clicked. (On an Apple IIGS® computer, the bell is the tone whose pitch and volume you can adjust from the Control Panel.)

If you select the Hilite option, the button area will be highlighted when clicked and the screen colors inside the button rectangle will be reversed (black to white and vice versa, orange to blue and vice versa, etc.). The highlighting will remain on screen until the button is clicked again, restoring the original colors, or until a new screen opens. Use the Hilite option to display the user's button choice as a new screen is loaded or to show which buttons on the screen your user has already chosen.

"Linking to" Buttons

Both the Link to Screen and the Text Entry buttons now offer the option to link to a button on the current screen, instead of linking to a different screen. A list of buttons on the current screen now appears at the end of the Link to Screen menu. (For more information on the Link to Screen menu, see page 58.) To link to a button, choose one of these buttons from the menu. Linking to a button allows greater flexibility in designing your screen. It also saves disk space. For instance, if you had several buttons that performed the same action (such as popping up a hint or speaking the same guiding phrase), you need only create one button now. You can then link all other buttons to the first button. With the Text Entry button, you can now link a no-match result to a Pop-up Text button which provides a hint and lets the user try again. This avoids the need to create an entirely new screen for a hint.

"Do Nothing" Buttons

Instead of displaying a "Button Info incomplete" prompt when clicked, buttons with no button type or incomplete information will now simply do nothing. However, these buttons can be highlighted or ring a bell when clicked. This means you can use "do nothing" buttons to highlight an area of the screen or sound an attention-getting tone without doing anything else.

Video Control Buttons

Video Control buttons can now include a command which stops sending commands to the videodisc player and waits for the user to click a button or press a key before continuing. To insert such a pause in a sequence of video commands, type **WT**. For example, the following Video Control button commands could be used to start the player and display a series of four slides (at video frames 350, 392, 524, and 216), with a key or button press required to advance from each slide to the next one:

SA FR350SE WT 392SE
WT 524SE WT 216SE
WT RJ

This command is useful in allowing browsers to determine how long to look at a video image before proceeding or in using *HyperScreen* to control video displays during a presentation to an audience. If you use the **WT** command, you may wish to include a "Click to Continue" message on your screen.

Improved Browsing

New Scanner Features

Three new improvements have been added to enhance the Scanner, allowing students with special needs, and especially physically disabled users, to more easily browse stacks:

- **Multiple Scan Speeds** To adapt to different abilities, you can set the scanner to three different speeds: **S** (Slow), **M** (Medium), or **F** (Fast). On Slow speed, the scanner moves from button to button every 5 seconds; on Medium speed, it moves every 3 seconds; on Fast speed, every second. To set the Scanner speed, select Browse Options from the **OPTIONS MENU** and make the appropriate choice. To reset the speed while browsing, press **Esc** and choose a different speed from the Browse Options box that appears. (See page 99 for more information on using the Browse Options box.)
- **Pausing the Scanner** Pressing the space bar now causes the scanning process to pause—stopping button outlining and clicking noises. Press a key or button to begin scanning again. Teachers can use this feature to engage students in other activities temporarily without the distraction of the scanner.
- **Automatic Pause** If the scanner cycles through all the buttons on a screen five times without the user making a selection, the scanner automatically pauses. To restart the scanner, press a key or button.

Keyboard-Only Browsing

When the scanner is not in use, the browser can now move the hand from button to button using the Arrow keys and then press **Return** to select the button. In version 1.0, this option was available only if no pointing device was attached. Now it is available even with a pointing device attached. Special-needs users who cannot use a pointing device will find this feature especially helpful; users of a pointing device may also find this selection method easier at times.

New Editing Features

Copy Screen

A new item, **Copy Screen**, can be selected from the **FILE MENU**. With this item, you can copy the entire contents of any screen in the stack to your current screen—including the screen type, buttons, transition, border, text, graphics, etc. **Copy Screen** makes it easy to create one screen, for instance the Home Screen, that can be a template for other screens in the stack. You would then copy the Home Screen to another screen and modify it as you chose. If you wish to copy only the graphic image of a screen for use as a background on another screen, select **Export Screen Image** from the **FILE MENU**, open the other screen, and then select **Graphic Background** from the **TOOLS MENU** to bring in the exported image. (See page 48 for more information about exporting screen images.)

Screen Info

A new item, **Screen Info**, can be selected from the **EDIT MENU**. When you select this item, you will see a window of information about your current screen displayed. The information includes the stack name, screen name, screen type, location in the stack, and a list of all the screen buttons with their types and special options. The letters to the right of each completed button indicate whether it is clickable (**C**), Do-on-opening (**D**), a Bell (**B**), or Hilite (**H**). (See the information on page 3 of this addendum for more information about the new Bell and Hilite options.)

New Button-Editing Features

DOUBLE-CLICKING TO SET A BUTTON'S INFO

When using **Set Buttons** from the **EDIT MENU** to place and size buttons, you can now double-click on a button (move the pointer to the button and press the Apple key, mouse, or joystick button two times in succession) to have the **Button Info** box appear. You can also still click once to select the button and then press **Tab** or **Ctrl-I** to call up the **Button Info** box. (See page 54 for more information about the **Button Info** box.)

VISIBLE BUTTON NUMBERS

After choosing **Set Buttons** from the **EDIT MENU**, the number of each button now appears in the upper-left corner of the outlined button rectangle. Finding and editing specific buttons, especially non-clickable buttons that are part of a Multi-button list, is much easier with this added feature.

Echo Command Reference Charts

The following charts are reprinted by permission from Street Electronics Corp.

Phoneme Codes

REMEMBER: To send phonetic codes, surround them with curly brackets { }.

SAMPLE WORD	DICTIONARY SYMBOL	PHONEME CODE
Vowels		
cat	a	A
lot	o	;
caught	o	*
let	e	E
see	e	&
hid	i	I
book	oo	Q
but	u	U
due	oo	:
about		.
Voiced Consonants		
let	l	L
many	m	M
no	n	N
sing	ng	/
red	r	R
this	th	(
very	v	V
wet	w	W
yes	y	Y
zero	z	Z
azure	zh	X
Diphthongs		
cake	a	@
tie	i	!
toe	o	O
pound	ou	#
toil	oi	?
you	u	%
Stop Consonants		
bat	b	B
dog	d	D
get	g	G
kick	k	K
pet	p	P
tie	t	T
check	ch	C
job	j	J

SAMPLE WORD	DICTIONARY SYMBOL	PHONEME CODE
"R" Colored Vowels		
car	ar	;R
chair	ar, er	@R
her	ur, er	'R
hear	er	&R
fire	ir	IR
for	or	OR
tour	oor	QR
hour	our	#R

Unvoiced Fricatives

fit	f	F
hat	h	H
see	s	S
she	sh	\$
think	th)

Inflection

Stressed - 3	Normal - 2	Reduced - 1	Schwa - 0
--------------	------------	-------------	-----------

Pitch

Rising - >	Flat - =	Falling - <	Pause - ,
------------	----------	-------------	-----------

A Sample Phoneme Vocabulary

A - @	H - 'C
And - AND	Hello - HELO1
Answer - A3NS'R	HyperScreen - H!3P'RSCR&N
Apple - A3P'L	
B - B&	I - !3
Byte - B!3T	Incorrect - INKORE3KT
	J - J@
C - S&	
Catalog - KA3DIL*G	K - K@
Correct - KORE3KT	Keyboard - K&3BORD
D - D&	
Decimal - DE3SIM'L	L - EL
Divide - DI1V!3D	
E - &	M - EM
Equals - &3KW'LS	Memory - MEM'R&1
Exclamation - EKSKL'M@3SHUN	
F - EF	N - EN
First - F'RST	No - NO
	Number - NUMB'R
G - J&	
Good - GQ3D	O - O3
	Off - *F
	On - *N
	Open - OP'N

P - P&
Program - PRO3GRAM

Q - K%3
Question - KWESC'N

R - ;R3
Return - R&T'R3N

S - ES
Sorry - S;R3&
Spell - SPEL

T - T&
That - (AT
The - (&3
Thousand -)#3ZS'ND

U - %3
Understand - UND'RSTA3ND

V - V&

W - DUBI%1
Where - W@R3
Wrong - R*/

X - EKS

Y - WI3
Yes - YES

Z - SZ&

Additional Commands

REMEMBER: To send Echo commands, surround them with square brackets [].

PITCH (n=1 to 63)

Flat [nF]
Intonation [nP]

VOLUME (n=0 to 15) [nV]

RATE

Compressed (Fast) [C]
Expanded (Slow) [E]

PRONUNCIATION

Words [W]
Letter-by-Letter [L]


PUNCTUATION

Some (#\$%&+ / <=> @) [S]
Most [M]
All (LF, CR, SPACE) [A]

DELAY (n=0 to 15) [nD]

Scholastic HyperScreen is a trademark of Scholastic Inc. Cricket and Echo are trademarks of Street Electronics Corp. Apple IIGS is a registered trademark of Apple Computer Inc.

Scholastic HYPERSCREEN™



Design and Programming	George Brackett
Reference Guide Author	Ellen Geist
Tutorial Author	Donna Miller
Video Control Author	Miguel Chavez
Teaching Guide Authors	Jennifer Howland, Ellen Baru
Graphics	Angela Greene
Published by	Scholastic Software 730 Broadway New York, NY 10003
Publisher	Peter Kelman
Director of Product Development	Philip Miller
Editorial Director	Amy McKinley
Project Editor	Debra Weinberger
Contributing Editor	Sara Anne Romanelli
Managing Editor	Pamela Lawson
Production Editors	Martine Coscia, Chuck Wahrhaftig
Print Production	Rick Scarbrough
Art Director, Print	Jenny Grant
Additional Support	Rachel Auslander
Director of Marketing	Susan Beecher

■ Scholastic Inc. New York Toronto London Auckland Sydney

Notice: This work is fully covered by the Copyright Law of the U.S. (Title 17 of the U.S. Code) and the Universal Copyright Convention. Unauthorized copying is strictly prohibited.

Software copyright © 1990 George Brackett. Published under exclusive license with Scholastic Inc. All rights reserved. User's Guide copyright © 1990 Scholastic Inc. Printed in the U.S. A. Published by Scholastic Inc.

Apple is a registered trademark of Apple Computer Inc. *Scholastic Slide Shop* is a trademark of Scholastic Software. *Super Story Tree* is a trademark of Scholastic Software. *Scholastic Graphics and Sound Booster Pack* is a trademark of Scholastic Software. *The Print Shop* is a registered trademark of Broderbund Software. *Scholastic SuperPrint* is a registered trademark of Scholastic Software. *816 Paint* is a trademark of Baudville. *MousePaint* is a trademark of Apple Computer, Inc. *Stickybear Draw* is a registered trademark of Weekly Reader. *Blazing Paddles* is a trademark of Baudville. *Graphics Magician* is a trademark of Penguin Software, Inc. *ComputerEyes* is a trademark of Digital Vision, Inc. *ThunderScan* is a registered trademark of Thunderware, Inc. *Pelican Graphics Converter* is a trademark of Pelican Software, Inc.

ISBN: 0-590-82303-5

12 11 10 9 8 7 6 5 4 3 2 1 1 0 1 2/9

CONTENTS

Introduction	7
About <i>Scholastic HyperScreen</i>	7
Terms	8
Classroom Uses	8
What You'll Need	10
What's in the <i>Scholastic HyperScreen</i> Package?	10
Making Legal Copies of <i>Scholastic HyperScreen</i> Disks	11
Getting Started	13
Loading the Program	13
Working With <i>HyperScreen</i>	13
Getting Help	15
Creating a Stack Disk	15
Saving Your Work on a ProDOS Disk	16
Formatting a ProDOS Disk	16
Starting a New Stack	16
Choosing a Text or Graphic Screen	17
<i>HyperScreen</i> Quick Guide	19
Overview	19
Designing <i>HyperScreen</i> Creations	19
Browsing Through a Stack from the Menu Bar	23
Reference Guide	25
PART 1: WORKING WITH <i>HYPERSCREEN</i>	26
The <i>HyperScreen</i> Home Stack	26
Opening Menus and Selecting Menu Items	27
How to Get Help	27
Escape	28
Using <i>HyperScreen</i> With Other Disks	28
The Disk Menu Box	28
Locating a File	29
The <i>HyperScreen</i> Menu Bar	30
The APPLE MENU	31
<i>HyperScreen</i> Home Stack	31
Create Stack Disk	31
Printer Setup	31
Pointer Setup	33
PART 2: DESIGNING A <i>HYPERSCREEN</i> CREATION	35
The FILE MENU	35
New Stack	35
Open Stack	37
Delete Stack	37
Browse	38
New Screen	41
Open Screen	43
Delete Screen	44
Save Screen	45
Preview Screen	47
Print Screen	48
Export Screen Image	48
Save Clip Art	49

Quit	49	PART 3: BROWSING THROUGH A <i>HYPERSCREEN</i> CREATION	101
The EDIT MENU	50	Browsing Through a Stack From the Menu Bar	101
Undo	50	Browsing Through a Stack From a Stack Disk	103
Cut	51	Tutorial: How to Make Your First <i>Scholastic HyperScreen</i> Creation	104
Copy	52	How Stacks Work: The Stack Design Chart	104
Paste	53	Loading the Program	106
Clear	53	The <i>HyperScreen</i> Menu Bar	106
Set Buttons	54	The Stack Disk	106
Set Button Info	57	The Stack	107
Choosing a Button Type	58	The Screen	108
Changing a Button Type	58	The Home Screen of "Whale Watch"	108
Button Types	58	Step One: Create Your Screen	108
Link to Screen	61	Step Two: Design Your Screen	109
Link to Stack	62	Add a Graphic Background	109
Multi-Button	64	Add Text	110
Pop-up Text	66	Add Clip Art	112
Sound/FX	68	Add an Opening Transition	113
Text Entry	73	Step Three: Set the Buttons	114
Video Control	74	Set Button Information	115
The TOOLS MENU	75	Step Four: Preview and Save Your Screen	118
Border	76	Step Five: Browse Through Your Creation	120
Opening Transition	77	The Intro Screen	121
Graphic Tools	77	The Map Screen	124
Brush	79	The Q/A Screen	128
Pen Line	80	The Types Screen	131
Frame	81	The States Screen	133
Block	82	The Stack End Screen	136
Ring	83	Editing Your <i>HyperScreen</i> Creation	136
Oval	84	Appendices	
Flood Fill	84	Appendix A: The Video Control Button	137
Type	86	Equipment You Will Need	137
Clip Art	86	Setting Up	137
Using the Clip Art Libraries	86	Using the Modem Port (Apple IIGS, Apple IIc, and Apple IIc Plus)	137
Selecting a Piece of Clip Art	87	Using The Apple II Super Serial Card	138
Coloring Your Clip Art	88	The Video Overlay Card	139
Graphic Background	89	Testing Your Setup	139
Using <i>HyperScreen</i> with Other Graphics Programs and Utilities	89	The Commands	141
Text Tools	89	Basic Commands	142
Text Editor	91	Advanced Commands	146
Special Feature: A Rounded-Corner Button Box	92	Glossary	154
Special Feature: Screen Arrows	92	Appendix B: Graphic Backgrounds, Clip Art, Fonts, Borders and Sound	156
Import Text	93	Appendix C: Educator's Guide to Software Copyright Policies and Ethics	168
The OPTIONS MENU	93	Index	173
Ink Color	94		
Selecting an Ink Color	94		
The <i>HyperScreen</i> Color Palette	95		
Border Color	95		
Video Key Color	96		
Brush Shape	96		
Pen Width	97		
Graphic Font	98		
Text Font	98		
Text Background	99		
Browse Options	99		
Correcting Mistakes	99		

INTRODUCTION

About *Scholastic HyperScreen*

When you use *Scholastic HyperScreen*, you are the author, creating visually engaging, lively, interactive multimedia lessons and presentations, databases, stories, and information displays. You'll design your *HyperScreen* creations screen by screen using a wide array of artist's tools, graphic backgrounds, fonts, clip art, and sound. Your screens can appear with special effects including wipes and checkerboard jumbles. You can even control a videodisc player or combine computer graphics, text, and video images on a single screen.

While the program is versatile and includes many sophisticated features, it is not difficult to use. Using the program's pull-down menus, you design your creations step by step. Teachers, computer coordinators, and students in grades 7 through 12 can use *HyperScreen*, but anyone can browse through a *HyperScreen* creation, once complete. *HyperScreen* lessons and presentations can be created for even very young children.

Scholastic HyperScreen includes these exciting features:

- On-screen buttons you create to perform a host of actions, such as playing a piece of music, opening a window of text, or branching from screen to screen.
- The option to create Text or Graphic screens.
- Full-color high-resolution graphics and clip art, compatibility with other graphics programs, and the option to create your own clip art and graphic backgrounds.
- A complete set of drawing tools to draw lines, ovals, rectangles, blocks, fill in areas with color, type in a variety of proportional fonts, and copy, flip, and move portions of the screen.
- A built-in text editor, and the ability to use text written with compatible word processors.
- High-quality music and sound effects.
- Special screen effects such as wipe, dissolve, flicker, and fade to black. Use these to simulate simple animation.
- Decorative screen borders.
- A Pioneer LD-V 4200 Laserdisc control built in for interactive video applications.
- On-screen interactive video when used with the Apple Video Overlay card.
- A library of sound clips, full-screen graphic backgrounds, clip art, borders, and fonts, as well as the ability to import these from *Print Shop*®, *Slide Shop*™, *Super Story Tree*™, or *Scholastic Graphic and Sound Booster Packs*™.

With *Scholastic HyperScreen*, you create a collection or *stack* of screens linked together with on-screen buttons. (See Terms, page 9, for a definition of a stack.) You save your stacks on self-booting disks that can be used without the program itself. By

clicking on-screen buttons your users follow a unique path through your *HyperScreen* creation based on choices you've designed. You can set up to fifteen buttons on a screen, selecting from an array of seven button types that perform these different actions:

Link to Screen This button links your user directly to another screen. Suppose you were designing a science lesson called The Solar System, for instance. You could have your user click a button to move on from the title screen.

Link to Stack This button links your user to another collection of screens. In your Solar System lesson, for instance, users could click a button marked Mercury and open a stack of screens taking them on an informational voyage to that planet.

Multi-button This special button activates a series of other buttons in succession. For instance, your user could click a Multi-button marked Mars to play a piece of martian-like music with a Sound/FX button, display a written description of Mars with a Pop-up Text button, then open a full-screen graphic of the planet with a Link to Screen button.

Pop-up Text This button displays a window of text in the center of the screen. You could design a map of the solar system, for instance, and your user could click on a planet to see some statistics about it "pop-up" on the screen. When clicked again, the pop-up text will disappear.

Sound/FX This button plays a sound clip: a piece of music, speech, or sound effect. In your solar system lesson, for instance, your user could click a button to hear a piece of "interplanetary" rock and roll.

Text Entry This button opens up an answer box for your user to type in a response. You decide on the correct response and then choose what screen will appear if the answer is right or wrong. You could query your user about the distance between planets, for instance, then open a screen of hints for the wrong answer and a screen with a new question for the right answer.

Video Control This button connects to a videodisc player, so your users can see a section of video you choose. By clicking a button marked Planet Earth, for instance, your user could see an actual video of the planet viewed from a satellite, with the proper videodisc. With the Apple II Video Overlay card, you can use the Video Control button to show both video images and *HyperScreen* graphics, text, and buttons on the same screen. For your solar system lesson, you could display the planet name and a symbol overlaying a moving video clip of the planet as if you were traveling toward it, viewing the control panel on a space voyage.

Since your *HyperScreen* creations can be run on any computer that meets the hardware requirements without the program disk itself, you can swap lessons, presentations, and databases with other teachers and schools. You can organize your students to design their own stacks alone or in groups. Using *HyperScreen* in this way, students develop problem-solving, information-organizing, and visual-thinking skills as they learn content. Students can exchange their creations as well.

Combine your educational expertise and imagination with the powerful capabilities of this program to create exciting lessons across the curriculum—social studies, math, science, art, music, literature, history, geography. While *HyperScreen* can be used alone, creations in various content areas such as science and technology, and social studies can be enhanced through the use of the *Scholastic Graphics and Sound Booster Packs™*.

Terms

Here are some helpful terms to know as you create with *HyperScreen*.

Button Buttons are areas you design and set on your screen that perform a variety of actions when clicked, such as linking screens, playing a sound effect, or linking to another stack.

Browse When you browse, you play or read through your *HyperScreen* creations by clicking the on-screen buttons. Using the Browse Options box, you choose which screen to begin browsing and other options. (See page 39 for more information on the Browse Options box.)

Click Clicking on an item refers to moving to it with your arrow keys or pointing device and clicking an Action button or a mouse button.

NOTE: In this User's Guide, using the arrow keys on the keyboard and pressing Return, or in some cases the Apple key, will also be referred to as clicking on an item or button.

Home Screen The first screen of every stack is automatically named the Home Screen by your program. You can change this name or keep it. Since your creations can become quite complex, the Home Screen can be useful as a home base or starting point.

Home Stack This is the stack you see when you load *HyperScreen*. From the buttons on the Home Screen, you can open other stacks such as the Introduction or Help stacks.

Preview This menu function shows you how your screen will look, including how buttons will function, but all buttons don't fully work as they will when you browse. Use this to check your screens quickly as you design them, without having to leave the design process to browse.

Stack *HyperScreen* organizes your screens together in an ordered collection called a stack. You create the order and organization of your stack with on-screen buttons.

Stack Design Chart Before you begin creating a stack, you may find it useful to draw a chart on paper and decide on your screens and buttons. You can also create a Stack Design Chart on-screen with the *HyperScreen* program, using clip art icons for each button.

Classroom Uses

HyperScreen is a powerful and versatile classroom tool, opening up new and varied ways to create interactive lessons, presentations, and stories. Here are just a few suggestions for its many uses:

- Create a dynamic display of student work from the school year for an open house, with parents clicking buttons to see each student's efforts.
- Have each student create a stack of information on a research topic, and then link these together in a single creation.

- Create instructional materials that branch to different levels of difficulty based on the answers your user gives to questions.
- Create interactive maps that can display information about each item clicked.
- Create history lessons, using real video clips of events.
- Simulate a voyage to another country, time, or planet, using interactive video and sound.

NOTE: You should think of HyperScreen Stack disks as a new type of teaching resource. For more information and additional classroom applications, see the Teaching Guide.

NOTE TO SPECIAL EDUCATORS: HyperScreen contains a Scanner feature which you can turn on to help your special education students read HyperScreen creations. Whenever there are choices for the reader to make, the buttons will be outlined one after another. The reader can then make a selection by pressing the Space Bar or clicking the Action button when his choice is outlined. For more information on reading lessons and turning on the Scanner, see Part 3: Browsing through a HyperScreen Creation, page 102.

What You'll Need

To use HyperScreen you'll need:

- An Apple IIe with 128K, IIc, IIc Plus, or IIGS
- A monitor
- At least one disk drive (a second drive is recommended)
- Blank disks for storing your HyperScreen creations

Optional:

- Joystick, mouse, or touchpad
- Printer
- Second disk drive
- A Pioneer LD-V 4200 Laserdisc player
- Apple Video Overlay card

What's in the Scholastic HyperScreen Package

The HyperScreen package includes:

- Disk A (Side 1: Scholastic HyperScreen program; Side 2: Introduction)
- Disk B (Side 1: Graphic Backgrounds, Clip Art; Side 2: Fonts, Borders, Sound)
- Sample Stacks disk

- This User's Guide
- Teaching Guide
- Legal Copy disk labels

NOTE: If you are using the 3.5-inch disk version, you will receive one disk only. The 3.5-inch Program Disk contains the HyperScreen Program, Introduction, Graphic Backgrounds, Clip Art, Fonts, Borders, Sound, and Sample Stacks.

Making Legal Copies of Scholastic HyperScreen Disks

The disks included in the Scholastic HyperScreen package are Archival disks. Follow the instructions below for either using the Archival disks for previewing Scholastic HyperScreen or for making Legal Copies once you have purchased the program.

For a complete description of your rights and responsibilities in copying disks and using the program, see the Scholastic Software License and Warranty Agreement included in your Scholastic HyperScreen package. Scholastic also encourages schools to read, discuss, and distribute copies of the ETHICS STATEMENT included as an appendix at the end of this manual.

The disks in this package are fully protected by copyright law. It is against the law to copy or in any way duplicate the disks or any portion of the program except under the terms expressly stated in these instructions and in Scholastic's Software License and Warranty Agreement.

If You are Previewing Scholastic HyperScreen

The 5.25-inch Archival disks are write protected to prevent damage or changes to their contents. Because Scholastic HyperScreen must write printer setup information back to the disk, you are permitted (despite the restrictions stated in Section 3 of the Software License and Limited Warranty Agreement for Noncopy-protected Software Published by Scholastic Inc.) to make a temporary Legal Copy of the 5.25-inch program disk when previewing Scholastic HyperScreen. This temporary Legal Copy must be erased at the end of the 30-day preview period if you decide not to purchase the program.

NOTE: If you have purchased the 3.5-inch version of this program, the same policies apply.

Once You Have Purchased Scholastic HyperScreen

Once you have purchased the package, you must make a Legal Copy of each Archival disk. You may not use the Archival disks for running the program. Use the Legal Copies instead.

To make Legal Copies of the Archival Disks, follow these instructions:

1. Use any standard copy program or function to copy the entire contents of each Archival disk onto one blank disk. If you are copying the Apple version of the program, use the Duplicate Disk function of your ProDOS® System Disk or a commercial disk copying program.

NOTE: Be sure to copy the complete contents of each disk. If the label on the Archival Disk indicates that it is double-sided, be sure to copy both sides. Do not change any directory or file names.

2. Your package includes Legal Copy disk labels. Use a soft-tipped marker to write the serial number from the enclosed Software License and Warranty Agreement in the space provided on each disk label.
3. Affix the appropriate Legal Copy disk label to each of the copies that you created in Step 1.
4. Store the Archival Disks in a safe place with a copy of the Software License and Warranty Agreement.

If a Legal Copy becomes damaged or defective, first try recopying the program from the Archival disk to the Legal Copy disk. If the program still does not work, the Legal Copy disk medium itself may be defective. In this case, copy the Program from the Archival disk to another disk as a temporary legal copy. Then send the defective Legal Copy disk to Scholastic at the address below for a free replacement. When you receive the replacement, erase the temporary legal copy that you made.

If an Archival disk is damaged or defective, send it to Scholastic at the following address for a free replacement:

Scholastic Software
Scholastic Inc.
P.O. Box 7502
2391 E. McCarty St.
Jefferson City, MO 65102

In Canada

Software from Scholastic
123 Newkirk Road
Richmond Hill, Ontario
Canada L4C 3G5


ProDOS is a registered trademark of Apple Computer, Inc.

GETTING STARTED

Loading the Program


To load the *HyperScreen* program, follow these instructions:

1. Insert the *HyperScreen* program disk (Disk A) with the label facing up (Side 1) in Drive 1 and close the disk drive door.
2. Turn on your monitor and computer. If the computer is already on, press the Control, Open Apple, and Reset keys at the same time.
3. In a few seconds you will see the title screen. After the title screen, the home screen of the Home Stack will appear. You can click on any of the on-screen buttons of the Home Stack or press Esc to begin using the features of the menu bar.



Working With HyperScreen

The Apple icon and the File, Edit, Tools, and Options headings at the top of the screen make up the *HyperScreen* menu bar. Each menu pulls down.




HyperScreen works with the keyboard, joystick, mouse, or touchpad. Though each works slightly differently, you can make selections in these two basic ways:

Keyboard: Use the Left or Right Arrow key (← →) to highlight the headings at the top of the screen. A pull-down menu will automatically open below the heading. To select a menu item, use the Up or Down Arrow key (↑ ↓) to highlight it, then press Return.

Pointing device: Use your pointing device to point to a heading at the top of the screen. Then click the button on your mouse, joystick, or touchpad to open the pull-down menu below it. (The button on your mouse, joystick or touchpad is called the Action button). To select a menu item, point to the item and click (press and release) the Action button.

NOTE: As you work, you can make the menu bar disappear at any time by pressing the Space Bar. Press any key to make it return.

At any point in the program, the active menus and menu items will appear in boldface on your screen. Inactive items will appear in dimmed type.



NOTE: In this User's Guide, highlighting an item and then pressing Return or clicking your pointer device is often referred to as "selecting" an item. Moving to an item or button with your pointer device and then pushing the Action button, mouse, or pressing Return (or in some cases the Apple key) is referred to as "clicking."

Getting Help

You can always browse through the Help stack to find information you need. Select *HyperScreen* Home Stack from the menu bar, then click on the Help Stack button.



The Help Stack displays a graphic of the menu bar. Click on the menu you wish to read about and a sample menu will appear. Then just click on the item you want.

If you can't find the information you need in the Help Stack, consult the appropriate section of the Reference Guide for help.

Creating a Stack Disk

You can save your *HyperScreen* creations on special Stack disks. These Stack disks are formatted disks that are self-booting. Once you create a Stack disk you will not need the program disk to use your creations.

Follow these steps to create a Stack disk:

1. Select Create Stack disk from the APPLE MENU.
2. A menu will appear asking you in which drive you want to create your Stack disk. If you have two disk drives, select Drive 2. With one disk drive, select Drive 1.
3. The program will prompt you to insert a blank disk in the drive you selected. After you insert the blank disk, press Return (keyboard) or click OK (joystick or mouse).

NOTE: Notice the carriage return symbol (↵) next to OK. This means you can either press the Return key or click the OK button.

If you have inserted a disk which is not blank, the program will ask if you are sure you wish to copy over the information on the disk. If you do not wish to erase the contents of the disk, press Esc or click Cancel. If you don't mind erasing the disk, press Return or click OK to begin creating a Stack disk.

4. The program will format your new Stack disk. After the disk has been formatted, you will be asked to insert a current Stack disk or Side 2 of the program disk. The first time you create a Stack disk you will need to use Side 2 of the program disk. After that, you can use Side 2 of the program disk, or any existing Stack disk. Follow the appropriate on-screen instructions for your choice.

NOTE: If you are using the 3.5-inch version, you do not need to insert a current Stack disk or Side B as described above. But if you only have one disk drive, you will need to swap disks between the program disk and your Stack disk.

5. The program will copy files from the existing Stack disk onto your new Stack disk. You will see the message "Cleaning Up" and the menu bar will appear. The disk is now ready to use as a Stack disk.

NOTE: If you have one disk drive, you will need to swap disks several times. Each time the program asks for the new Stack disk, insert the disk you are creating. Each time the program asks for Side 2 of the HyperScreen Program disk, insert it (or any other existing Stack disk).

Saving Your Work on a ProDOS Disk

Whenever possible, save your creations on a Stack disk. Stack disks are self-booting, and the *HyperScreen* program automatically checks for a Stack disk when saving or loading screens. If you need extra room on your disk, and you do not need your creation to be self-booting, you can save it on any ProDOS formatted disk. You can then browse through the stack by selecting Browse from the FILE MENU. (See Browsing Through a Stack From the Menu Bar, page 23, in the Reference Guide.)

Formatting a ProDOS Disk

Follow these steps to create a ProDOS formatted data disk:

1. Open the APPLE MENU and select Create Stack Disk.
2. Indicate which slot and disk drive you are using at the prompt.
3. Insert a blank disk into the drive you selected in Step 2 and press Return or click OK.
4. The program will format your data disk and title it STACKDATADISK. When the program asks you to insert Side 2 of the *HyperScreen* program disk, press Esc or click cancel to end the procedure and return to the menu bar.

Your data disk is now ready to use.


NOTE: Whenever possible, use Stack disks to store your HyperScreen creations.

Starting a New Stack

To begin a New Stack, select New Stack from the FILE MENU on the menu bar.

You will be prompted to insert a Stack disk. If the disk you wish to save your stack on is not in the drive, insert it.

This Disk Menu box will appear:



Type in the name for your new stack at the cursor and click OK or press Return. (For more details on using the Disk Menu box, see page 28 of the Reference Guide. For more about selecting New Stack, see page 35.)

The Text or Graphic Screen box will appear under the title Home Screen. The next step will be to choose a Text or Graphic screen.

Choosing a Text or Graphic Screen


You can create two types of screens in your *HyperScreen* stacks: Text screens and Graphic screens. Text screens use less disk space than Graphic screens. Different tools on the TOOLS MENU are available for each.

With both Text and Graphic screens, you use any of *HyperScreen*'s decorative borders, opening transitions, and the full range of on-screen buttons.

- With Text screens you can use several text fonts and the Text Editor, a built-in word processor. You can import blocks of text written with compatible word processors using the Import Text feature. Text screens can also include curved button boxes, and on-screen arrows created with designated keys. Choose a Text screen when you wish to use only text and to save disk space. This can be very important when creating a complex stack with many screens.
- With Graphic screens, you can use the complete set of *HyperScreen* drawing tools and a variety of graphic type fonts. You can also select from *HyperScreen*'s library of full-screen graphic backgrounds and clip art. Choose a Graphic screen when you wish to use these graphics and tools.

You can combine both Text and Graphic screens in the same stack.

Once you choose your screen type, the new empty Home Screen will be automatically saved. This helps keep your screens in order in your stack. The menu bar will appear with the TOOLS MENU pulled down.



The menu is divided into three sections. The first section contains tools available for both Text and Graphic screens. The second section contains tools available only with Graphic screens. The third section contains features available only when creating Text screens. Items you cannot use after you have chosen a screen type will appear dimmed. (See The TOOLS MENU, on page 74 of the Reference Guide for more detailed information.)

HYPERSCREEN QUICK GUIDE

Overview

You might want to begin using *HyperScreen* by browsing through the Intro stack on the *HyperScreen* Home Stack. This will give you an overview of *HyperScreen*'s features. Click on the Intro icon. Press Esc when you are done browsing to return to the menu bar.

In addition, the Tutorial on page 104 gives step-by-step instructions for creating an interactive presentation. This is an excellent way to learn how to create *HyperScreen* stacks.

Designing your own stack requires these basic steps:

1. Begin at the Home Screen. Choose a Text or Graphic screen.
2. Design your screen using the diverse fonts, clip art, graphics, borders, opening transitions, and drawing tools available with *HyperScreen*.
3. Set your buttons and complete button information.
4. Preview, edit your work, and then save your screen.
5. Continue making screens you linked to or new screens. When you finish your creation, save and browse through it to see how it works as a whole.

Designing *HyperScreen* Creations

If you would like to begin by creating your own stack, follow the instructions below:

Create a Stack Disk

1. Load the *HyperScreen* program (Disk A, Side 1).
2. Select Create Stack Disk from the APPLE MENU.
3. Follow the instructions that appear on the screen to create a Stack disk.

Begin a New Stack

1. Insert a Stack disk in a disk drive.
2. Select New Stack from the FILE MENU.
3. Enter a name for your stack.
4. Choose whether to make your home screen a Text or Graphic screen.

REMEMBER: A Text screen can contain text, a border, opening transition, and the full range of buttons, and a Graphic screen can contain text, a border, opening transition, buttons, clip art, and graphic backgrounds. Text screens take up less space than Graphic screens. If you are creating a complex stack, choose Text screens whenever possible.

5. The Home Screen will open.
6. Use the TOOLS MENU to create the screen. The menu items you can use for your Text or Graphic screen, the active menu items, will appear in bold text. (You can make the menu bar disappear as you work by pressing the Space Bar. Press Esc and it will return.)

Before you select graphic or sound options, or a font from the disk, make sure the appropriate disk and the appropriate side of the disk containing Graphic Backgrounds, Clip Art, Fonts, Borders, and Sound, is inserted in a drive.

The OPTIONS MENU contains special features. With the OPTIONS MENU, you can set the brush shape or graphic font, for instance. The Ink Color, Brush Shape, Pen Width, and Graphic Font options can also be called up with control keys while using the graphic tools. This eliminates the step of pressing Esc and moving to the OPTIONS MENU to make changes. While using a graphic tool, press Esc to move to the menu. Press Esc again to return to the place from which you escaped. See page 93 for more on the OPTIONS MENU. You can also click onto the OPTIONS MENU on the Help Stack from the *HyperScreen* Home Stack to see a list of control keys.

You can use the EDIT MENU to clear the screen, copy and paste art, or undo mistakes.

7. Use Opening Transition from the TOOLS MENU to set a visual effect for a screen. You can choose from a variety of effects such as Dissolve, Flicker or Fade to Black.
8. Use Set Button from the EDIT MENU to create your buttons. Select Set Buttons. Then read the following section.

Set Buttons


After you've visually designed your screen, you'll set buttons in place and choose your button types.

Select Set Buttons from the EDIT MENU. With the cursor, draw a box on the screen where you want to place your button. Your button location will be shown by a dotted outline frame. Clicking anywhere on the button produces an unbroken outlined frame with a small block in the lower right corner. You can "drag" from anywhere inside this frame with your pointing device to move your button location. Click on and drag (move) the small block in the corner (the handle) to size your button.

To choose your button type and fill in the information for its action, press Esc and return to the menu bar. Then select Set Button Info from the EDIT MENU. Your buttons appear as dotted outlined frames. Click onto the button you want to set.

NOTE: You can also set your button information without returning to the menu by clicking it and then pressing Ctrl-I or the Tab key.

A Button Info box will appear on your screen. The button number at the top indicates the button in the order it was created. By clicking on the outlined box around the word <None> that appears next to "Type:" you can scroll through a list of button types and make your choice.



Button Types

Link to Screen

With this button, your user will move directly to another screen that you choose.

Once you choose a Link to Screen button, this selection will appear in your button information box. Now by clicking <None> that appears next to "Screen:" in your Button Info box, you can scroll through a list of screens and make your choice.

Link to Stack

With this button, your user will move to a stack that you choose.

Once you select this type of button, follow the above procedure, but choose from the list of stacks that appears. Be sure the stack you want to link to is in a drive.

Multi-button

With this button, your user activates a series of other buttons in the order you choose.

Click <None> next to "Buttons:" in the Button Info box. Then type the button numbers according to your desired order in the Multi-button List box, separated by commas.

Pop-up Text

With this button, text of your choice will appear in a window in the center of your screen.

After you select this button, click on <None> next to "Text:" and type in the text you wish to appear in the Pop-up box.

Sound/FX

With this button, your user will hear a selected sound clip.

After you choose this type of button, place the disk with your sound clip in a drive. Click the <None> next to "Effect:" on the Button Info box. Then select your sound from the Disk Menu box that appears.

Text Entry

With this button, you can create and size a Text Entry box. Then, depending on the response the user types in, one of two screens you select and design will appear.

After you choose this type of button, click on the box next to "Match Pattern:". A box to type in your matching text will appear. Type in your matching text entry and press Return.

The program will check your matching pattern against the text entered by the user and branch to one screen on a match and another on a no-match (the screens could actually be the same). The matching text can be a single word, but a simple code allows you to specify a more complicated match pattern (see page 68 for instructions).

Select which screen to open if your user's response matches (If "Yes:") or not (If "No:") by clicking the <None> data next to these options on the Button Info box.

Set your entry blank by selecting Set Entry Blank from the Button Info box. A text line-high cursor box will appear on your screen. Position and size the entry blank as you do buttons. When clicked, the Text Entry box will place the cursor in the location you've set.

Video Control Button

Choose this button to control a videodisc player and play a preselected portion of a videodisc.

After selecting a video control button, you need to identify a port and type in a command by clicking or pressing Return next to "Port:" and "Command:" on the Button Info box. See page 73 for more detailed information on this button.

Do On Opening Buttons and Clickable Buttons

By clicking the check box next to Do On Opening on the Button Info box, you can choose to make any button an opening button. This means that this button will automatically go into action when the screen appears. You can only have one opening button per screen. By designating an opening button, you could have music play when the screen changes, or have the Text Entry box appear automatically so your user knows to type in the answer without clicking on a button.

You can make a button non-clickable by clicking the check box next to Clickable to clear the X inside. You might want to make opening or Multi-buttons non-clickable so your users can't click them on their own.

Preview Your Screen

Select Preview Screen from the FILE MENU to view your screen. You can click buttons, but Link to Screen, Link to Stack, and Text Entry buttons will show the link rather than do it. You can toggle between showing and hiding buttons by pressing B. You can also turn off sound on your on-screen buttons, choose to show buttons, or use

the scanner by selecting these from the Browse Options item on the OPTIONS MENU before previewing your screen.

Save a Screen

You must save your screen when you have finished working on it, or after you make any changes or additions to it (including changing a screen link). Follow the steps below to save your screen:

1. Make sure the Stack disk is inserted in the drive.
2. Select Save Screen from the FILE MENU. Exit the name of the screen if you like. Press Return or click OK to save this page of your stack.

Continue Creating Your Stack

Begin the second screen by selecting Open Screen from the FILE MENU. Select the screen you want to work on. Your choice will include any of the screens you named as links in your buttons. You can also select New Screen to begin an entirely new screen that is not yet linked to any others. Then repeat the steps for designing, setting buttons, and saving for each screen in your stack.

When you are done, select the Browse option from the FILE MENU if you wish to browse through the stack.

Browsing Through a Stack From the Menu Bar

Browsing through a stack from *HyperScreen's* menu bar is useful if you want to test your stack while you are designing it. To do this:

1. If you are not already working on the stack you want to browse through, choose Open Stack from the FILE MENU. Then select the stack you want to browse through from the Disk Menu box.
2. Before selecting Browse, you can set browse options by selecting Browse Options from the OPTIONS MENU. You can choose to turn sound on or off, show (outline) or hide your buttons, or turn the scanner on or off.
3. Now select Browse from the FILE MENU. If you have not selected other options, you will begin at the first screen, with sound, without buttons showing, and without the Scanner feature. Click the on-screen buttons to browse through your stack.
4. Press Esc while browsing to have the Browse Options box appear. You can change the controls or select the screen at which you want to begin. To return to the menu bar, click Cancel or just press Esc again.

NOTE: Remember, you can always reach the Browse Options box as you browse by pressing Esc. To continue browsing after selecting from the Browse Options box, be sure to click the circle on Begin at: (●) This Screen. Press Esc again to stop browsing and return to the menu bar.

You can also browse through a stack you have created and saved onto a Stack disk simply by inserting that disk into your computer and turning the computer on. You can also use a program selector to run the program STACK.SYSTEM on the Stack disk.

For additional ease in browsing, you can press a single key for these functions.

Press:	To:
B	Show clickable buttons in an outline on screen. Hide outline by pressing again.
arrow keys	Move the pointer hand if a mouse is attached, but not if a joystick or touchpad is attached. Move the pointer hand from one button to the next in button number order, if no pointing device is attached.
spacebar	Toggle between one-pixel long and ten pixel long jumps of the pointer hand across the screen, when using the arrow keys to move.
<	Back up to the last screen you viewed, all the way back to where you began browsing at the current stack.

REFERENCE GUIDE


This Reference Guide contains detailed instructions for using each feature of *HyperScreen*. It also contains instructions for designing screens, using buttons, and creating stacks with *HyperScreen's* special features.

The quickest way to familiarize yourself with the program is to go through the Getting Started section at the beginning of this User's Guide. That section contains information on loading the program and creating Stack disks, as well as a Quick Guide outlining the basic steps in *HyperScreen* creation. You may also want to work through the Tutorial on page 104 which leads you step-by-step through designing a sample stack. Then, for detailed instructions on using any of the features in the program, refer to this Reference Guide.

PART 1: WORKING WITH HYPERSCREEN

The HyperScreen Home Stack

When you load the *HyperScreen* program (see Loading the Program, page 13), after the title screen, you will see this Home Screen of the Home Stack.



On the Home Screen the buttons are labelled icons designating stacks you can browse through. Move the pointer hand with your joystick, mouse, touchpad, or arrow keys to the button you choose. Click on the stack you wish to see by pressing and releasing the Action button on your joystick, mouse, or touchpad, or pressing the Return key.

NOTE: In this Reference Guide, clicking on a button or item refers to both these methods:

Keyboard: Move the pointer (hand or arrow) to an item or button using the arrow keys and then press the Return key. In some cases, as noted, you will use an Apple key instead of the Return key.

Joystick, mouse, or touchpad: Move the pointer (hand or arrow) to an item or button with your pointer device and then press and release the Action button.


By clicking buttons on the built-in Home Stack, you can browse through an introduction to *HyperScreen* or the Help Stack.

Press Esc to bring the menu bar into view. See Opening Menus and Selecting Menu Items below for more about using the menu bar. To make the menu bar disappear as you work, press the Space Bar. Press any key to bring it back into view.

You can reach the Home Stack again at any time by selecting *HyperScreen* Home Stack from the APPLE MENU (see page 31). You can also browse through the Home Stack after bringing the menu bar to your screen by selecting Browse from the FILE MENU. For more detailed information on browsing through stacks, see page 35 of this Reference Guide.

Opening Menus and Selecting Menu Items

When you bring the menu bar into view the FILE MENU will automatically be opened. You'll see a pointer arrow instead of a pointer hand on your screen. Your screen will look like this:



The Apple icon and the headings at the top of the screen comprise the *HyperScreen* menu bar. Each menu heading is a pull-down menu. Choose the pull-down menu you wish to use by using the Left or Right Arrow keys (← →) or by pointing to the menu heading and clicking to open the menu. Items that appear dimmed cannot be used at that time.

To select an item from a pull-down menu:

Keyboard: Use the Up or Down Arrow key (↑ ↓) to highlight a menu item. Then press the Return key.

Joystick, mouse, or touchpad: Point to a menu item and click (press and release) the Action button.

How to Get Help

The *HyperScreen* program contains a built-in Help Stack with information on each menu item. To browse through this stack, select the *HyperScreen* Home Stack from the APPLE MENU. Then click the Help button on your screen. You will see a graphic of the menu bar. Click the heading for the menu containing the item you want. The menu will open, just as if you were using the menu bar. Now click any item and information about it will appear.

IMPORTANT: If you are working on a screen, you will be warned to save it before you select the *HyperScreen* Home Stack (or browse through any stack); otherwise, any new work you've done will be lost. (See Save Screen, page 45.)

If you can't find the information you seek in the Help stack, consult the appropriate section of this Reference Guide.

Escape

Press the Escape key (Esc) to return to the menu bar, reach the Browse Options menu while browsing, or to cancel an option. If you press Esc to return to the menu bar while using any graphic tool or the Text Editor, you can return to the point you escaped from by pressing Esc again. Using a mouse or joystick, you can escape in these additional ways:

- Whenever a pointer cursor is on screen, place the pointer in the extreme upper right-hand corner of the screen and leave it there for a few seconds.
- When a submenu is on the screen, click anywhere outside the menu. You can also click the Cancel button within the menu.

Using HyperScreen With Other Disks

The wide array of graphics, sounds, and fonts you can use with *HyperScreen* are not stored on the *HyperScreen* Program disk. To use the program with the other disks you'll need, follow the guidelines below.

Once you've loaded the *HyperScreen* program, you don't need to keep the Program disk in the drive to use most tools and menu features.


You will need to insert the program disk to create a Stack disk, set printer options, print a screen, or browse through the *HyperScreen* Home Stack.

Removing the program disk will free your drive(s) for Graphics and Sound disks, Stack disks, or other data disks.

Each time you select a *HyperScreen* option requiring information stored on another disk, for example a border, sound, or a piece of clip art, you will see a Disk Menu box.

The Disk Menu Box

The Disk Menu box tells you what disk is in the drive in current use and what is stored on that disk.



The top line of the Disk Menu box shows the name of the disk in use. The window below lists the files or folders you can select from. (Files are often stored in folders.) To scroll through the list, use the arrow keys or click on the arrows to the right of the window. To make a selection, press Return after a file has been highlighted or click the file or folder you want to open. When you select a folder, the list of files in that folder will appear in the window.

The rectangle above the window displays the disk name until you open a folder. When you open a folder, the disk name in the rectangle is replaced by the folder name, preceded by the Open Folder icon (). The Open Folder icon tells you that the window contains only those files stored in that folder (not necessarily all the files on the disk).

Below the window, you'll see the name of the item you selected from the *HyperScreen* pull-down menu. This tells you what the program is looking for. For example, Clip Art tells you the program is looking for Clip Art files. While all folders on a disk will appear in the window, the program will only list files of the type being loaded. In other words, if you select the Clip Art option from the TOOLS MENU, the program will only list Clip Art files, even though there are graphic backgrounds on the disk. If there are no files of the selected type in the disk or open folder, you'll still see the disk name at the top and the file type you selected below, but no files will be listed.

To use the Disk Menu box, follow these steps:

- To scroll through the list of files or folders, use the arrow keys (keyboard) or click the arrows to the right of the window (joystick or mouse).
- To open a folder, highlight that folder, then press Return (keyboard) or click on OK at the bottom of the menu box (joystick or mouse). The list of files in that folder will appear in the window. An Open Folder icon and the folder name will replace the disk name in the rectangle above the window.

REMEMBER: The open folder icon tells you that the window contains only those files stored in that folder, not necessarily all files on the disk.

- To choose a file, highlight the file you want, then press Return (keyboard) or click OK (joystick or mouse).
- To close a folder, press the \ key (keyboard) or click Close (joystick or mouse).
- To change drives, press Tab (keyboard) or click Drive (joystick or mouse).
- To return to the menu bar, press Esc (keyboard) or click Cancel (joystick or mouse).

Locating a File

When you open a folder, it will list only the files in that folder. If you select Clip Art from the TOOLS MENU, for example, and the Clip Art folder does not appear in the menu, you may not have the disk containing Clip Art in the drive. If you can't find the file you want, follow the steps below:

1. Make sure the correct graphic, clip art, fonts, borders, and sound, or Stack disk is in a disk drive.
2. Make sure the program is reading the disk drive containing the disk you wish to use. (If the program is not reading the correct drive, press Tab or click on Drive to change drives.)

The HyperScreen Menu Bar

The *HyperScreen* menu bar contains five pull-down menus:


APPLE MENU Use this to browse through the *HyperScreen* Home Stack, create a Stack disk, set up your printer, or choose a pointing device.

FILE MENU Use this to create, open, delete or browse through a stack. Use this menu also to begin, open, delete, save, preview or print your screens. Using this menu you can also export a screen image as a picture file, save clip art, or quit the program to ProDOS.

EDIT MENU Use this to undo mistakes or clear the screen. You can also use the Cut, Copy, and Paste options on your Graphic screens. Use this menu, also, to set buttons and button information on your screens.

TOOLS MENU Use this to select *HyperScreen's* drawing tools, graphic and text editing features while creating screens. Import text and graphics or clip art with this menu. Use this menu also to select borders and transitional effects for your screens.

OPTIONS MENU use this to select ink, border, and video key colors (see page 95 for details about video key color). You can set the brush width, pen width, and graphic font from this menu for use with *HyperScreen's* tools. You can also select a background color and font for your text screens, or set options for browsing through stacks.



The APPLE MENU

The APPLE MENU contains four items: *HyperScreen* Home Stack, Create Stack Disk, Printer Setup, and Pointer Setup.

HyperScreen Home Stack

Select this to browse through the Introduction or Help Stack. Click on the button for the stack you wish to see. (For more about the *HyperScreen* Home Stack, see page 13.)

To use to the menu bar, press Esc.

You can browse through this stack again once the menu bar is in view by selecting Browse from the FILE MENU. If you press Esc after choosing browse, you'll see the Browse Options menu. (For more information on Browse Options, see page 39.) Press Esc again to bring the menu bar back.


Create Stack Disk

Select this to create a Stack disk. Stack disks are specially formatted *HyperScreen* data disks that you use for saving your stacks. Stack disks are self-booting. This means that when you have finished your stack(s), you can load the Stack disk directly into a computer and browse through a stack without using the *HyperScreen* program disk.


To create a Stack disk, see Creating a Stack Disk in the Getting Started section of this User's Guide.

Printer Setup


Select this from the APPLE MENU to set the printer setup for your computer. The Printer Setup menu will appear on your screen:



To change the printer, interface, or interface slot, move the outlined box over the item you want to change and press Return, or click the item. When the item is selected, a menu will appear listing the various options available. Select the item that matches your printer setup. The item you choose will replace the old information on the Printer Setup menu. For example, to change the interface from Apple IIc, IIGS Port to Apple Parallel, move the outlined box over Apple IIc, IIGS Port and press Return (keyboard) or click Apple IIc, IIGS Port (joystick or mouse).



The Interfaces menu will open. Now select Apple Parallel.



Apple Parallel will appear on the Printer Setup menu.

IMPORTANT: HyperScreen has been tested with the printers and interface cards listed on the Printer Setup menus. If your printer or interface card is not on the list, experiment with the ones that are listed. If this doesn't work, you will need to find another system to print your screens. If another system isn't available, save your screen as a screen image by selecting Export Screen Image at the FILE MENU. Then use a print utility to print the image. Or, load the image into any compatible graphics program that can print standard single hi-res graphics. (See Using HyperScreen with Other Graphics Programs and Utilities, page 89, in this Reference Guide.)

The last item on the Printer Setup menu determines whether the program will add a linefeed at the end of each line as it prints. Selecting this item toggles between linefeed and no linefeed. If you're not sure whether to turn linefeed on or off, print a sample screen (see Print Screen, page 48). If the screen looks correct, leave the setting as it is. If the lines are printing over each other, you'll have to turn the linefeed on. If you notice extra blank lines in your printout, turn the linefeed off.

When you're satisfied with the printer setup, press Esc to return to the menu bar. You'll see the prompt, "Saving Printer Setup..." on your screen. Any changes you made will be saved on your program disk. You won't have to repeat this process unless you want to change the printer setup.

Pointer Setup


Select Pointer Setup from the APPLE MENU to choose whether you wish to use a mouse, keyboard mouse, joystick, or graphic tablet with HyperScreen.

When you load HyperScreen, the program automatically activates any pointing device you have properly attached to your computer. The keyboard is always active, whether or not you have a pointing device attached. This means you can always use the arrow keys to move the highlight bar and the Return key to make selections. However, to use the arrow keys with the drawing tools or buttons the Keyboard Mouse option (using the keyboard as a mouse) must be turned on. The Keyboard Mouse is automatically turned on if you don't have a joystick or touchpad attached or if you are using the mouse. It is automatically disengaged if you are using a joystick or touchpad.

At times you may want to change your pointing device selection as you work. For example, when drawing, it's sometimes easier to use the keyboard mouse (the arrow keys) instead of a joystick.

You can set up a special browse mode by turning off all the pointing devices. When you do this, the pointer hand will move from button to button by pressing a single arrow key.

After you select Pointer Setup, the Pointer Setup box will appear on your screen. The darkened circles indicate the current setup.



To change the setup, follow these steps. With the keyboard, use the arrow keys to move the outlined box to the "on" circle for the pointing device you want to use, then press Return to darken the circle by your selection. Or, use your joystick or mouse to click your selection. You can also use the Tab key to move from option to option.

When you are finished, press Esc (keyboard) or click outside the menu (joystick or mouse) to return to the menu bar. The Pointer Setup you chose will remain active until you select a different device or quit the program.

NOTE: If you are using an Apple IIGS computer with a mouse, be sure you activate your mouse from the Control Panel of your machine. For information on getting to the Control Panel or setting options on the Control Panel see your IIGS user's manual.

PART 2: DESIGNING A HYPERSCREEN CREATION

The FILE MENU

The FILE MENU is divided into five sections.




- The first section contains the menu items to create a new stack, open an existing stack, or delete a stack.
- The second section, between the dotted lines, contains the item to browse through a stack.
- The third section contains the menu items for working with the screens of your stacks: begin a new screen, open an existing screen, delete a screen from the stack, save, preview, and print a screen.
- The fourth section contains the menu items to export a screen image as as a picture file or to save clip art.
- The fifth section contains the Quit item letting you quit the program to ProDOS.

New Stack

Select New Stack to create a new stack. Follow these steps:

1. Insert your Stack disk in a drive. (If you do not have a Stack disk, create one now. See Creating a Stack Disk, page 15.) You can also create a new stack on any ProDos formatted disk, but these stacks won't be self-booting (see Saving Your Work on a ProDos Disk, page 16, of the Getting Started section).
2. Select New Stack from the FILE MENU.

3. The Disk Menu box will open.



The label at the top of the disk will say STACKDISK. The names of the stacks, if any are saved on this disk, will appear in the menu window. (If a different disk name appears, make sure you have inserted a Stack disk or the program is reading the correct drive.)

REMEMBER: Pressing the Tab key or clicking the Drive button will tell the program to read another drive.

4. A blinking cursor will appear in the box beneath "Create New Stack as...". Type a name for your stack. The stack name can be up to 12 characters long. *HyperScreen* automatically prints the name in capitals, so you do not need to shift. Stack names must begin with a letter. The only punctuation that can be used in a stack name is a period. If you press the Space Bar to insert a space between words in your stack name, a period will automatically appear instead.


NOTE: This name does not have to be the complete name of your stack. For example, if your stack is titled "Trip to an Undiscovered Star" you can enter the file name as TRIP.TO.STAR.

When you finish typing the name, press Return or click the OK button.

5. You will see the prompt, "Creating stack file..." appear on your screen. The Home Screen box will appear for you to choose to make a Text or Graphic screen. This same box appears with a different title when you select New Screen or Open Screen to a named but unworked screen. Since you are beginning a stack, this first screen is automatically named the Home Screen. Later, when you save this page, you can change this name. But if you are designing complex stacks, the Home Screen name acts as a home base for your creation. To continue creating your new stack, follow the instructions for beginning a new screen (see New Screen, page 41).

Open Stack

Choose Open Stack from the FILE MENU to load an existing stack saved on a disk. The Disk Menu box will appear:



Select the stack you want. (For help with using the Disk Menu box, see page 28.) You will then see the Home Screen or first screen of your selected stack with the menu bar above and the TOOLS MENU opened. You are now ready to work on your screen. You can also move to any of the other menus. (See page 13 for a chart of the menu items.)


NOTE: At any time you can hide the menu bar on your screen by pressing the Space Bar. Press Esc to bring the menu bar back in view.

If you have created a new stack but not yet saved any screens, you'll see the Home Screen box. Follow the instructions for beginning a new screen on page 17.

Delete Stack

Choose Delete Stack from the FILE MENU when you want to permanently erase a stack from your disk. A deleted stack cannot be retrieved.

The Disk Menu box will appear.



Select the stack you want to erase. A warning message will appear on the screen reminding you that once you delete a stack, you cannot retrieve it. You cannot use the Undo feature in the EDIT MENU to bring back a stack once you have deleted it.

If you do not want to delete the stack, press Esc or click Cancel at this warning message to return to the menu bar.

If you want to delete the stack, press Return or click OK. If you choose to delete, the screen will say, "Deleting the Stack. . ." and your stack will be deleted.

If you delete the stack you are working on, you'll see the items in the second section of the FILE MENU dimmed, and you must open a new or existing stack to make them available again.


IMPORTANT: Never press Open-Apple-Ctrl-Reset while HyperScreen is deleting a stack. Pressing Reset while a stack is being deleted could damage your Stack disk.

Browse

Browse is *HyperScreen's* key feature. Select Browse to move through the screens and information on them by clicking buttons. When you select Browse, you'll begin at the stack and screen that are currently open.


NOTE: If you have not yet saved your current screen, you will be prompted to save or any new work will be erased. Be sure to save your screen. Then select Browse again.

Your screen will open with any Do On Opening button if you have selected these. (See page 76 for more on Opening Transitions and page 56 for an explanation of Do On Opening buttons.) The menu bar will disappear and a pointer in the shape of hand will replace the arrow pointer on the screen. All the buttons will now be fully operational.



To use a button on your screen, place the pointer hand over a button and click by pressing the joystick button, mouse button, touchpad, Apple key, or Return key. See the Set Button Info section of this Reference Guide for a complete description of *HyperScreen* buttons and their uses.

If you press Esc while browsing, the Browse Options box will appear. (If you press Esc immediately again you'll stop browsing and return to the menu bar.)



The darkened circles on the Browse Options box show the current setting. To change a setting:

Keyboard: Use the the arrow keys to move the outlined box over the setting you want and then press the Return key to darken the inside of the circle. You can also move from option to option by pressing the Tab key.

Joystick, touchpad, or mouse: Click the setting you want.


You can also move from option to option by pressing the Tab key.

From the Browse Options box, you can choose these options:

- You can choose to have sound on or off.
- You can choose to show the buttons, having them appear in an outlined rectangle on screen. Only "clickable" buttons will show. (See page 56 for an explanation of clickable and non-clickable buttons.)
- You can choose to have a scanner step automatically through the buttons to assist special-needs users (see page 10 for more about the Scanner).
- You can begin browsing at the current screen, another screen, or cancel the Browse Options box and return to your screen and menu bar.

If you select Begin at: This Screen from the Browse Options box, the current screen will appear with the pointer hand ready to click buttons.

If you choose to begin at another screen, you'll see the Begin At Screen menu.



Select the screen at which you want to begin browsing and then press Return or click OK. (For additional help with using this type of menu, see page 43.)

REMINDER: To stop browsing and bring the menu bar into view on the current screen, press Esc from the Browse Options box.

You can also preset browse options from the OPTIONS MENU on the menu bar. (See the section in this Reference Guide on the OPTIONS MENU for more about this menu.)

Once you select Browse Options from the OPTIONS MENU, the Browse Options box will appear.

After you set the options from the OPTIONS MENU, you will return to the menu bar with the OPTIONS MENU opened. To begin browsing, using your selected options, you must select Browse from the FILE MENU.

You can also use this feature of the OPTIONS MENU to set the Browse Options for your users if you are creating a self-booting Stack disk. (See page 103 in Part 3: Browsing Through a HyperScreen Creation for more on browsing through self-booting Stack disks.)

For additional ease in browsing, you can press a single key for these functions.

Press: To:

B Show clickable buttons in an outline on screen. Hide outline by pressing again.

arrow keys Move the pointer hand if a mouse is attached, but not if a joystick or touchpad is attached.

Move the pointer hand from one button to the next in button number order, if no pointing device is attached.

Space Bar Toggle between one-pixel long and ten-pixel long jumps of the pointer hand across the screen, when using the arrow keys to move if a mouse is attached, but not if a joystick or touchpad is attached.

< Back up to the last screen you viewed. You can continue all the way back to where you began browsing at the current stack.

Esc Have the Browse Options box appear. You can change the browse options and begin browsing once more or Press Esc again to stop browsing.

See Terms, page 9, in the Reference Guide for a quick definition of Browse.

New Screen


Select this from the FILE MENU to add a new, untitled screen to your stack. Once you select New Screen, a screen named Untitled is added to the list of screens on the screen menu in your computer's memory. But until you save and name your new screen, it won't be added to your stack. (See Save Screen, page 45, for instructions on naming and saving screens.)

NOTE: Select New Screen to add new, untitled screens only. If you have named blank screens during the process of setting buttons and you wish to work on one of these, select Open Screen instead. (See Open Screen, page 43, for details on using Open Screen.)

Choosing a Text Screen or a Graphic Screen

After you select New Screen, the Text or Graphic Screen box will appear with the heading Untitled at the top. This is the point at which you must choose a Text or Graphic screen.


REMEMBER: Different tools are available for Text and Graphic screens. (See page 18 for the tools available for each.) Text and Graphic screens are also stored in different formats on your disk. Because Text screens are simpler, they occupy less disk space, which is important to consider if you are planning a complex creation, linking many screens and stacks.



To choose your screen type, move the outlined rectangle to your choice with Tab or the arrow keys and press Return, or click your choice. Follow these rules when selecting the type of screen:


- Choose Text Screen to design a screen that presents only textual information. Text screens can also include a border, opening transition, background color, ink colors, and all button types. Type your text using the Text Editor, a built-in word processor listed on the TOOLS MENU. A special feature of the Text Editor allows you to create rounded boxes for your buttons and arrows on your Text screens. You can also import text from compatible word processors, *Super Story Tree* Text pages, or *Slide Shop* Text slides. (See the Import Text section in this Reference Guide on page 92 for more about these features.)
- Select Graphic Screen when you want to design a screen that contains graphics. With Graphic screens, you can add graphic backgrounds and clip art, and you can use the *HyperScreen* drawing tools to create original artwork. You can also add text in a variety of graphic fonts.

When you select Text Screen from the Text Screen or Graphic Screen box, the TOOLS MENU will open, with the Text Screen tools appearing in boldface type.



You are now ready to begin working on this Text Screen.


When you select Graphic Screen from the Text Screen or Graphic Screen box, the TOOLS MENU will open, with the Graphic Screen tools appearing in boldface type.



You are now ready to begin working on this Graphic Screen. (See the TOOLS MENU section of this Reference Guide, page 74, for a detailed description of the text and graphic tools.)


Open Screen

Select this item from the EDIT MENU to load an already named or worked on and saved screen. The Open Screen menu will appear. After you've created several screens on a stack, the Open Screen menu might look something like this.




NOTE: Only the first five screens will appear on the Open Screen menu. To scroll through the other screens, use the Up and Down Arrow keys (keyboard) or click the arrow boxes beside the window (joystick or mouse). Pressing the < and > keys will skip to the beginning and end of the list respectively.

Two kinds of icons appear next to the screen names on the Open Screen menu. They are:

() Blank screen: This means the screen was named with a Link to Screen or Text Entry button, but has not been worked on yet.

NOTE: Named but unworked screens should be selected with Open Screen, not New Screen.

() Worked-on screen: This means the screen was worked on and saved with the Save Screen item.

Select the screen you want. If you load a blank screen, the Text Screen or Graphic Screen box will appear (See Choosing A Text Screen or Graphic Screen, page 17.) If you load a screen that has already been worked on, that screen will appear. Use the *HyperScreen* tools to edit or finish the screen.

Adding Screens to the Open Screen Menu

You add screens to the Open Screen menu in these two ways:


1. Each time you use the New Screen item from the EDIT MENU, an Untitled screen will be added to the Open Screen menu (but not saved on disk). Once you name and save your new screen with the Save Screen item, it will be saved on disk and will appear on the Open Screen menu with a filled icon next to it.
2. Each time you create a Link to Stack or Text Entry button from the EDIT MENU, you can choose to link to a New Screen. (See Link to Stack button, page 61, and Text Entry button, page 68, for more about these button types.) You will give the new screen a name. That screen name will be added to the Open Screen menu, when your current screen is saved.

Delete Screen

Select this item to delete a screen from your stack. A warning message will appear on the screen reminding you that once you delete a screen it can't be retrieved. You can't use the Undo feature from the EDIT MENU to bring back a screen once you've deleted it.

If you do not want to delete the screen, press Esc or click Cancel at this warning to return to the menu bar.

If you choose to delete the screen, the Delete Screen menu will appear.



Select the screen you wish to delete from your stack. (For help with selecting from this type of menu, see page 43.) The screen will be deleted from the disk and the Screen menu. Then you will return to your screen with the FILE MENU opened.

NOTE: You cannot delete your current screen while it appears on your monitor. You must leave another screen open and then delete the original screen following the instructions above.

NOTE: You cannot delete the Home Screen (the first screen in a stack).


Save Screen

As you create your stack, you must save each screen before moving on to the next screen. You should also save your screen periodically as you work on it to avoid accidentally losing valuable work. Select Save Screen from the FILE MENU to save your screen on a Stack disk or a ProDOS formatted disk.

Save on a Stack disk whenever possible. (See page 15 for instructions on creating a Stack disk). If you need to save on a ProDOS formatted disk, these same instructions for saving apply. (See Saving Your Work on a ProDOS Disk on page 16 for more details about ProDOS formatted disks.) No matter which type you use, make sure the disk you save to contains the stack you are working on.

To save your screen, insert the disk containing your current stack in the disk drive. Then select Save Screen from the FILE MENU.

The Disk Menu box will appear. The name of the stack you are working on will appear below the dimmed list of stacks in Save Screen heading. The original name of your screen will appear in the Name box. If you are saving a New Screen, the name Untitled will appear in the box.



Follow these rules when saving your screen:

- To keep the screen name, press Return or click OK.
- To change this name, edit the name or press Ctrl-X to erase the old name and enter a new one. (If you are using an Apple IIGS, you can also use the Clear key to erase the name.)

If the program cannot locate your current stack on the disk in your drive, you'll be prompted to save on your original disk. Insert the disk containing your current stack in your drive, and click OK or press Return to continue.

Disk Space

The number in the upper right-hand corner of the Disk Menu box tells you how much space is available on your disk. Use this number to help estimate whether you'll have enough space available on your Stack disk for your stack.

You can store about 75 Text screens and a third as many Graphic screens on a 5.25-inch disk. (This estimation is for all Text or all Graphic screens. But remember you can mix Graphic and Text screens in the same stack, so these numbers are only approximate.) For more space, you might consider using 3.5-inch disks. *HyperScreen* allows you to create up to 200 screens per stack.

NOTE: You cannot separate a stack on two disks. You will be prompted when you are running out of disk space. (You could use a Pop-up Text, and Link to Stack Multi-button sequence to prompt your user to insert a different disk containing a continuation stack. See page 64 in the Multi-button section of Set Button Info.)


Preview Screen

Select this item from the FILE MENU to preview how your screen will look and how your buttons will work when you browse through your *HyperScreen* creation. Preview operates with your previously set browse options. (To show or hide buttons, turn sound on or off, or turn the scanner on or off, set these options from the Browse Options item on the OPTIONS MENU.) If you have chosen this, your screen will open with an Opening Transition, a special opening screen effect you select from the TOOLS MENU. (See page 76 in the TOOLS MENU section of the Reference Guide for a complete description of Opening Transitions.) If you have designated a button as a Do On Opening button, it will work as your screen opens. (See page 56 for a description of Do On Opening buttons.)

The pointer hand will appear and you can click on any clickable buttons. Buttons that act on the current screen will work just as they do while browsing, but buttons that link to other screens or stacks will show a box indicating the exact screen or stack link. Press B to toggle between showing and hiding buttons. Press Return or click OK on this box to continue. (See Set Buttons in this Reference Guide for a full description of all button types and their uses).


If you want to preview just the screen image without the menu bar, press the Space Bar. (You will not see any opening transitions, click any buttons, or see any links, as you would with Preview Page.) Press any key to return to the menu bar.

NOTE: Preview Screen differs from Browse on the FILE MENU. Use Browse to work your way through your entire *HyperScreen* creation, view any screen, or to use all buttons on a screen, even link to stack or screen buttons. Use Preview Screen to check your work and view buttons on the current screen.



Print Screen

Select this item from the FILE MENU to print a screen. You can print Text or Graphic screens in black and white, or in color if you are using the ImageWriter II® with a color ribbon. When you select Print Screen from the FILE MENU, the Print Screen box will appear on your screen:



The information at the top of the box displays the current printer setup. If the information is incorrect, press Esc, move the outlined box over the Cancel circle and press Return, or click the Cancel circle at the bottom of the Print Screen box. Then follow the instructions in the Printer Setup section, page 31, in this Reference Guide.

If the information is correct, you can then choose to print in two sizes: one screen or three screens per page. Make sure the circle for your choice of screens per page is darkened and change it if you wish.

Check to see if the paper in your printer is positioned correctly and your printer is set to Select or On-line. Then make sure the outlined box is positioned over the Begin circle and press Return or click to start printing. You can stop printing at any point by pressing Esc.

If you choose to begin, and don't have a printer attached, your screen image will appear to be frozen. Press Esc to make the menu bar appear and continue.

Export Screen Image

Select this item from the FILE MENU to save a *HyperScreen* image when you want to save the graphic image only, for instance, to edit and work on with a compatible paint program, for instance. Once you've saved your screen image on disk, you can bring it back onto a screen of your current stack using Graphic Background from the TOOLS MENU. (See page 88 for a complete description of using Graphic Background.)

NOTE: When you export an image, *HyperScreen* treats the file as a graphic background, NOT as a screen. This means no button settings or information are saved, and the exported screen image is not part of the stack you are working on. If you want to use the image as a screen with buttons in a stack, be sure to select the Save Screen item in addition to the Export Screen Image item.

To save your *HyperScreen* image for export to a compatible program:

1. Insert a ProDOS formatted disk into the disk drive.
2. Select Export Screen Image from the FILE MENU.
3. When the Disk menu appears on your screen, type a name for the file and press Return or click OK.

Save Clip Art

Select Save Clip Art from the FILE MENU to save original art as clip art. The contents of the area of computer memory called the clipboard will be saved on your disk as clip art. The current clipboard contains the last piece of clip art you may have loaded or any part of a screen you copied or cut. You can always check to see what is in the current clipboard by selecting Paste from the EDIT MENU. (See the sections on Cut, Copy, and Paste, beginning on page 50 in the EDIT MENU section of this Reference Guide.)

With *HyperScreen* you can create your own full-color clip art libraries by cutting or copying, and saving sections of your screens. Follow these steps:

1. Use the Copy or Cut tool from the EDIT MENU to frame and select the area of your Graphic screen that you want to store as clip art. Choose Copy to leave the original image intact and Cut if you wish to remove the image. You can copy or cut up to approximately one-half of the screen. (For instructions, see Copy, page 51, and Cut, page 50.)

NOTE: Once you have framed and selected the area of the screen that you want to save as clip art, you can press the H to flip the area horizontally or the V key to flip the area vertically. Pressing the H or V key again will flip the area back to its original position.

2. Insert a ProDOS formatted disk or a Stack disk into the disk drive. Then select Save Clip Art from the FILE MENU.
3. When the Disk Menu box appears on your screen, type a name for your clip art. Then press Return or click OK.

You can create original art to store as clip art. You can cut or copy portions of graphic backgrounds and save them as clip art. Try copying pieces from the Sample Stacks and saving them as clip art to use in your own stacks. You can also color and save clip art from existing clip art libraries.

The colors may shift if you move your homemade clip art across the screen. When this happens, shift the clip art slightly until the color looks correct.

Quit

Select Quit from the FILE MENU (or press ⌘-Q) to quit the program to ProDOS. If you have not saved your work, the program will display a message warning you that any work you've created or edited on a screen and have not saved will be lost forever.

The EDIT MENU

The EDIT MENU is divided into three sections.

- The first section contains the Undo function for undoing the last step you've taken on a Graphic screen.
- The next section contains what you need to Cut, Copy, and Paste on a Graphic screen, and to Clear any screen.
- The last section contains the functions to create buttons on your screen, including drawing, sizing, moving, and setting the information for what each button will do.

Undo

Select Undo or press Ctrl-Z, while using a graphic tool from the TOOLS MENU, to delete the last addition you made to your Graphic screen. If you decide that you want to restore that work, select Undo again before you do anything else and the work will reappear in its original form. (See the TOOLS MENU section beginning on page 77 for more about using graphic tools to design your screens.)

The Undo command works only on the last work you added to your graphic screen. If, for example, you use the Flood Fill option to color a piece of clip art, and then decide you don't like the color, you can select Undo. The color will be removed from the screen. If you select Undo again, the color will return. However, if you then use another drawing tool, choosing Undo will not remove the color from the screen.

NOTE: On a Text screen, the only thing you can Undo is adding a border or border color.

Cut

Select this option to cut a block (rectangular section) of your Graphic screen. You can move and stamp that section anywhere on your screen. You can also save the block as clip art and store it for future use. (See Save Clip Art, page 49, for directions on saving.) Cut also works in conjunction with the Paste option if you want to stamp the block on another screen of the current stack or another stack.

To cut a block of your Graphic screen:

1. Open the EDIT MENU and select Cut.
2. Move the cursor (a cross on the screen) to one corner of the section that you want to cut. While holding down the Apple key (keyboard) or Action button (joystick or mouse), move your cursor to the opposite corner until you have framed the portion you want to cut. The largest portion that you can cut is approximately one-half of the screen.
3. Release the Apple key or Action button and the section will be cut from your screen. White screen will appear instead of the section you have cut. The section you have cut will appear below the white area ready for pasting.

NOTE: Once the cut portion appears on the screen, you can press the H or V key to flip it horizontally or vertically. Pressing the H or V key again will flip the portion back to its original position.

4. Use your cursor to move the section around the screen. Place the cut portion where you want it to appear, then press the Apple key or Action button to stamp the section on the screen. You can stamp the cut portion as often as you wish on a screen.

NOTE: The Apple color monitor may cause the colors in your cut section to change as you move it around the screen. If the colors of the piece you are moving are incorrect, gently move it to the left or right before stamping the section on your screen.

5. If you don't wish to stamp the cut portion on another part of the screen, simply press Esc and it will disappear.

NOTE: When you press Esc, the cut portion will be held in the area of computer memory called the clipboard. You can restamp it on the current screen, another screen, or even a different stack by selecting Paste later. You can also save the section as clip art. (See page 49 on saving clip art.) When you cut or copy another section, or turn off your computer, the cut portion will be replaced or deleted from the clipboard and you can no longer restamp it.

HINT: You can use Cut to erase your mistakes. For example, if you make a mistake while working on a white screen and you cannot use the Undo function, simply cut out the section and press Esc.

Copy

Select this option to copy a block (rectangular section) of your Graphic screen. You can move and stamp that block anywhere on your screen. You can also save the copied portion as clip art and store it for future use. Copy also works in conjunction with the Paste option if you want to stamp the block on another screen of the current stack or another stack. (See Paste, page 52, and Save Clip Art, page 49, for more information.)

To copy a block of your Graphic screen:

1. Open the EDIT MENU and select Copy.
2. Move your cursor to one corner of the area that you want to copy. Hold down the Apple key (keyboard) or Action button (joystick or mouse) and move your cursor until you have framed the area you want to copy. (The largest area that you can copy is approximately one-half of the screen.)
3. Release the Apple key or Action button and a copy of the section will appear on your screen.

NOTE: Once a copy of the section appears on the screen, you can press the H or V key to flip it horizontally or vertically. Pressing the H or V key again will flip the copied portion back to its original position.

4. Use your cursor to move the section around the screen. Place the section where you want it to appear, then press the Apple key or Action button to stamp the copied portion on the screen. You can stamp a section as often as you wish on a screen.

NOTE: The colors in your copied portion may change as you move the section around the screen. If the colors in your section are incorrect, gently move your section to the left or right before stamping the copied portion on your screen.

HINT: You can use Copy to erase your mistakes. For example, if you make a mistake while working on a white screen and you cannot use the Undo function, simply copy a white block and stamp it over your error.

In some cases, it may help to copy a section that includes extra background area surrounding the object you want to move. When you reposition that block, the background of the portion will cover the original object.

NOTE: You can press Ctrl-B to cycle through opaque and transparent backgrounds and inverse images of the clip art you copy. For example, if you are using Copy to place clip art on a colored background, you can press Ctrl-B to create an opaque white background for the clip art. Then use Flood Fill to color the clip art and the surrounding white areas. If you are working on a dark background, press Ctrl-B to cycle through to the inverse image. The clip art background will remain transparent, but the black lines will appear in the opposite color of the background (for example, white on black, red on blue). See page 49 for directions on saving your clip art created with Copy.

Paste

Select this item to "paste" art as many times as you want on the current Graphic screen or on other Graphic screens.

When you select Paste, the program uses the block or clip art, including cut or copied art, that is in the clipboard to the current screen. This feature saves valuable time when you need to use a piece of clip art, or a block of your Graphic screen, several times in a single session.

When you select Paste, the clip art or graphic block that is in the clipboard will appear on your screen. Move your cursor to position the block or clip art. Then press the Apple key (keyboard) or Action button (joystick or mouse) to paste it on the screen. You can stamp the contents of the clipboard on a single Graphic screen as many times as you want.

To transfer a block and paste it on a new Graphic screen:

1. Save the screen you are working on.
2. Use the Load Screen option from the FILE MENU to load the new screen.
3. Select Paste from the EDIT MENU.

The block from the clipboard will reappear on the screen. Stamp it as many times as you wish. If you like, follow the above steps to paste the block from the clipboard on another Graphic screen.

NOTE: You can press Ctrl-B to cycle through opaque and transparent backgrounds or inverse images of clip art. For example, if you are using Paste with clip art which has been placed on a colored background, you can press Ctrl-B to create an opaque white background for the clip art. Then use Flood Fill to color the clip art and the surrounding white areas.

Clear

Select this option to clear a Graphic or Text screen and start over.

When you clear a screen, everything on that screen will be permanently cleared, including all text, graphics, sounds, screen effects, and screen links. Only the screen name remains the same.

The program will first display a warning that you cannot undo clearing the screen. This means the Undo item from the EDIT MENU will not work. If you do not wish to clear, press Esc or click Cancel. If you want to clear the screen, press Return or click OK to go on. You are left with a blank screen. Choose whether you want the cleared screen to be a Text or Graphic screen. Then create the new screen. (See Choosing a Text or Graphic screen, page 17.)

NOTE: If your screen has been saved, you can undo clearing a screen by selecting the screen from the Load Screen menu again.

Set Buttons

Using Set Button and Set Button Info from the EDIT MENU, you can create on-screen buttons that can be clicked to move from screen to screen, link to stacks, and perform a variety of other actions. Setting buttons and button information enables you to use the full range of HyperScreen's interactive multimedia capabilities in designing your HyperScreen creations.

NOTE: Before you set buttons and button information, you will probably want to create your screen using HyperScreen's graphic and text tools.

Select Set Buttons from the EDIT MENU to create, resize, move, or delete a button from your screen. You can set up to 15 buttons on one screen.

To create a button:

1. Select Set Buttons from the EDIT MENU.
2. The menu bar will disappear from view and any current buttons will appear as dotted outlines. Move the on-screen pointer arrow to one corner of your desired button location and click by pressing the Action button or the Apple key. A cursor in a cross-shape will replace the arrow.
3. Holding down the apple key or Action button, drag the "rubber band" frame to create your button. The frame will shrink and expand as you move the cursor.
4. When you've stretched a frame in the location and size you want, release the Apple key or Action button. You'll see a dotted line frame left on the screen, indicating the button you've just created.

NOTE: Once you create a button, you can view or set the button information without having to return to the menu bar and choose Set Button Info. Just click anywhere within or on the dotted-line frame to select the button, then press Ctrl-I or Tab. Set your button information following the instructions beginning on page 55.

If you return to the menu bar after setting buttons, you need to select Set Buttons again from the EDIT MENU to bring the dotted-line button frame into view so you can resize, move, or delete buttons.

To resize a button:

1. Click within or on the dotted-line frame of the button to select it. A solid line with a small filled block in the lower right-hand corner (the resize handle) will replace the dotted line.

NOTE: In this Reference Guide, the solid line frame with the resize handle that appears when you click a button in a dotted-line-frame will be called the selected button frame. The dotted line frame will simply be called the button frame. When you select Set Buttons from the EDIT MENU all buttons you've created will appear in button frames.

2. Place the arrow cursor directly on the handle and click your pointing device or press the Apple key. Holding down the Apple key or Action button on your pointing device, pull from the handle to resize the button frame.
3. Once the button is your desired size, click the arrow cursor anywhere outside the button to remove the selected button frame.

To move a button, keeping it the same size:

1. Move the arrow cursor anywhere within the button frame.
2. Press and hold down the Apple key or Action button of your pointer device.
3. Keeping the arrow cursor within the button, drag the selected button frame to the desired location. Then release the Apple key or Action button.
4. Click anywhere outside the button to remove the selected button frame.

To delete a button:

1. Click inside the button frame to select it.
2. Press the Delete Key.

REMEMBER: You can Press Ctrl-I or Tab after selecting a button to view or set button information. (See Set Button Info, page 55.)

Set Button Info


Select this item to set, view, or change information for selected buttons on your screen. Button information sets up what the action of the button will be when clicked.

When you choose Set Button Info from the EDIT MENU, the menu bar will disappear and any buttons you have created with Set Buttons, or have set information for as well, will appear as a dotted-line button frames.

NOTE: You can click buttons in two different ways. Using your pointing device, move the cursor to any point within the button, then press and release the Action button on your joystick, touchpad, or mouse. Or, using the keyboard, move the cursor with the arrow keys, and then press the Apple key.

To set button information for a button you have created with Set Buttons, first select Set Button Info from the EDIT MENU. Move to the button frame around the button you want to set information for, then click. The Button Info box will appear.

REMINDER: You can also reach the Button Information box from the Set Button mode, without having to return to the menu bar and select Set Button Info. Click on the button you want to select and press Ctrl-I or Tab.



At the top of the Button Info box, you'll see the number of the button you have selected. For instance, Button 3, as in the sample above. Buttons are numbered in the order they are created.

The button type appears next to "Type:". Because no type has been set in the sample above, <None> appears next to "Type:". Press Return or click the outlined box around <None> to select one of the seven button types or to change the button type. See Choosing a Button Type, on page 57, for detailed information on selecting a button type.

Below the type you will see the Clickable check box. It will automatically be checked with an X unless you change it. This box should be checked if you want to be able to click the button while browsing through your stack. To make it non-clickable, click the check box or move the outlined box down with the arrow key or Tab, and then press Return. The X in the check box should disappear. To replace the X, click again.

Make your buttons non-clickable in these instances:


1. When you want the button to work only on the screen opening, and not be clicked again once the screen opens. (See Do On Opening, below, for an explanation of Opening Buttons).
2. When you want the button to work only as part of a Multi-button sequence. (See Multi-button, page 62, for an explanation of this button type).

You'll see the Do On Opening option below the Clickable option. The check box beside this item will not be checked unless you change it.

Check Do On Opening when you want the button to automatically work when the screen opens without having to be clicked. Use Do On Opening, for instance, to have a piece of music play as the screen opens, or have a message appear in a Pop-up Text box. (See the instructions for Sound F/X, page 66, and Pop-up Text button types on page 64.)

You can create simple simulated animation using a Do On Opening button as a non-clickable Link to Screen button, linking two similar but slightly different graphic screens. By combining this with the Flicker opening transition you can make it appear as if your graphics are moving. For other samples of Do On Opening buttons, see the Tutorial section of the Reference Guide.

To check Do On Opening, click the check box beside it, or move the outlined box over the check box and press Return.




If you wish to clear the check box again, repeat the steps above.

You can only choose one button on your screen as an opening button.

Press Esc to accept the current information in the Button Info box.


Choosing a Button Type

To select a button type, move the outlined box next to "Type:" in the Button Info box and press Return, or move the arrow cursor next to "Type:" with your pointing device and click. The Button Type menu will appear.



REMEMBER: Only five choices appear on this type of menu at any given time. Since there are seven button types, use the arrow keys or click the arrow icons to scroll through the additional choices. You can also press < or > to skip to the top and bottom of the list.

To choose your button type, highlight your selection, then click OK or press Return. Or simply click your selection. The Button Info box will appear with your selected type filled in. If you choose Sound/FX, for instance, this Button Info box will appear:



For instructions on completing button information for each button type, see page 54.

Changing a Button Type

To change a button type, follow the same steps as choosing a button type.


For instructions on completing button information for each button type, see page 54.

NOTE: You can change any of the information in the Button Info box by clicking that option or name, or by moving the outlined box over the option and pressing Return.


Button Types

Link to Screen A Link to Screen button, when clicked as you browse, will move to and open a specific screen you selected from the current stack.

When you select this button type from the Button Type menu (see Choosing a Button Type, page 57), the Button Info box that appears will look like this.




To choose the screen to which your button will link, move the outlined box over the <None> next to "Screen:" in the Button Info box and press Return, or move the arrow cursor to <None> with your pointing device and click. The Link to Screen menu will appear.



REMEMBER: Only five screen choices appear on the menu at any given time. Use the arrow keys or click the arrow icons to scroll through the additional choices. You can also press < or > to skip to the top and bottom of the list. (See page 43 for additional help with using this type of menu.)


You can link your button to a new screen, the previous screen, an existing screen, or stack end.

- Select New Screen to link to an entirely new screen that you'll then name. When you select New Screen, this Link to Screen box will appear.




Type a name for your new screen. It can be a maximum of 15 characters long. If you make a mistake in typing, use the Delete key to back up and delete single characters, or press Ctrl-X to delete the entire name and start again. You'll find it helpful to choose a name that refers to what you plan to include on that screen.

You can press Esc to cancel your entry and return to the Button Info box to change any button information. To accept the name, press Return or click OK. If you type the name BLACK HOLE for a new screen to link to in your TRIP.TO.STAR stack, as an example, this Button Info box will appear:




Press Esc to accept the button information and return to your current screen.

Your named new screen will be added with an () icon to the list of screens on the Open Screen menu so you can design it later. (See page 43 for instructions on opening a new screen you've named and saved with a Link to Screen button.) Once you save the current screen with the button linked to a New Screen, an unworked screen will be saved on disk with that name.

- Select Previous Screen to link your screen back to the screen that appears just before the current one when you browse through your stack.
- Select Stack End when you want to link your screen to an option to end browsing. When you select Stack End, on clicking, the Browse Options box will appear on the current screen. To end, the user then clicks Cancel on the options box. You can also continue browsing by selecting another screen. Since clicking on a Link to Screen button that is linked to Stack End won't connect you to another screen (the Browse Options box appears on your current screen), you might want to design that screen as an end screen.
- You can link your screen to any previously named screen, including the Home Screen, by selecting it from the Link to Screen menu.

Once you select your connecting screen, the Button Info box will appear with your selection next to "Screen:" If you select a screen named RED GIANT, for instance, that you created, this Button Info box will appear.




Press Esc to accept the button information and return to the current screen.

You can change the screen link on a Link to Screen button at any time as you create your stack. Select Set Button Info from the EDIT MENU and click the button, or after selecting Set Buttons, click the button and press Ctrl-I or Tab. When the Button Info box appears, click the name next to "Screen:" or move the outlined box over the screen name and press Return. Then follow the same steps above for choosing your screen link.


NOTE: You can change any of the information in the Button Info box by clicking that option or name, or by moving the outlined box over the option and pressing Return.

Link to Stack A Link to Stack button, when clicked as you browse, will open the Home Screen (or first screen) of a stack you have selected.

When you select this button type from the Button Type menu (see Choosing a Button Type, page 57), this Button Info box will appear.



To choose the stack to which your screen connects, first insert the disk with your desired stack in the disk drive. Then move the outlined box over <None> next to "Stack:" in the Button Info box and press Return, or move the arrow cursor to <None> with your pointing device and click. The Stack Disk Menu box will appear.



Scroll through the list of stacks and select your choice for the button link. (See page 28 if you need further assistance in using the Disk Menu box.) The Button Info box will appear with your selected stack next to Stack.

For example, if you selected the stack called Space Warp from the Disk Menu box, this Button Info box would appear.

The screenshot shows a window titled "Info: Button 1". Inside, it has the following fields: "Type: Link to Stack", a checked checkbox for "Clickable", an unchecked checkbox for "Do On Opening", and a text field for "Stack:" containing the text "/STAC...SPACE.WARP". At the bottom, it says "Press Esc to accept."

Press Esc to accept the button information and return to your current screen.

You can change the stack link on a Link to Stack button at any time during the design process. First, bring up the Button Info box for the button you wish to change. (For directions, see Set Button Info, page 54.) When the Button Info box appears, click the name of the stack next to "Stack:" or move the outlined box over the stack name and press Return. Then follow the same steps above for choosing your stack link.

NOTE: You can change any of the information in the Button Info box by clicking that option or name, or by moving the outlined box over the option and pressing Return.

Multi-button A Multi-button, when clicked, activates a series of other buttons in succession. For instance, you could click a Multi-button to play a piece of music with a Sound/FX button, display a clue with a Pop-up Text button, then link to a new screen with a Link to Screen button.

NOTE: When you set up a Multi-button using pop-up text buttons, your user must click to remove pop-up text from the screen before another button is activated. Any Link to Screen or Link to Stack button ends the multibutton series.

When you select this button type from the Button Type menu (see Choosing a Button Type, page 57), this Button Info box will appear.

The screenshot shows a window titled "Info: Button 1". Inside, it has the following fields: "Type: Multi-button" (highlighted with a box), a checked checkbox for "Clickable", an unchecked checkbox for "Do On Opening", and a text field for "Buttons:" containing the text "<None>". At the bottom, it says "Press Esc to accept."

NOTE: In the Button Info box, use the Tab key or the arrow keys on the keyboard to move the outlined box over the information or option, and then press Return. Another method is to point to the information or option with your pointing device and click. In this Reference Guide, both these methods will be referred to as "selecting information."

To set up your button sequence, select <None> beside "Buttons:" in the Button Info box. The Multi-button List box will appear.

The screenshot shows a window titled "Multi-button List". It contains a large empty text area for entering the sequence of buttons. At the bottom, it says "Press Esc to accept."

You can create your Multi-button list of buttons in any sequence as long as you type the numbers in order, separated by commas (or at least one non-numerical character between).

For example, you can type 1, 3, 12 or Button 1, Button 3, Button 12 for the same button sequence.

You can repeat buttons.


Any Multi-buttons or buttons you haven't chosen a type for yet, won't work as part of your sequence. Once you include a button that links to a screen or stack, any buttons you list after that won't work as part of the Multi-button.

Press Esc to accept the Multi-button list.


You may want to set small nonclickable buttons in unused areas of the screen as part of your Multi-button sequence. For example, a Multi-button series might include (1) a Pop-up Text button prompting your user to place a disk containing another stack in a drive, (2) a Link to Stack button to the end of this series. To examine the Introduction button as an example of this on the Home Stack, bring the menu bar into view and click Set Button Info from the EDIT MENU.

Pop-up Text A Pop-up Text button, when clicked, displays a window of text in the center of the screen. Click again to have the pop-up text disappear. You could use this button type to display hints, special suggestions, or extra information.

When you select this button type from the Button Type menu (see instructions for Choosing a Button Type, page 57), this Button Info box will appear.




To type in the text for your pop-up text window, select <None> beside "Text:" in the Button Info box. The pop-up text box will appear.



You can type up to five lines of 22 characters in the Pop-up Text box. Press Esc to accept the text you've typed. The portion that fits will appear in the Button Info box. Press Esc again to accept the button information and return to the current screen.

REMEMBER: You can change any of the information in the Button Info box by clicking that option or name, or by moving the outlined box over the option and pressing Return.


When you click a Pop-up Text button while browsing, your screen might look something like this:




The window of pop-up text will always appear in the center of the screen in the System 8 font.

Sound/FX A Sound/FX button, when clicked, will play a sound clip, including music, special sound effects, or digitized sound such as speech.


When you select this button type from the Button Type menu (see instructions for Choosing a Button Type, page 57), this Button Info box will appear.




To choose the sound clip your Sound/FX button will play, first insert the disk containing your desired sound in your disk drive. You can use the sounds from *Super Story Tree*, *Slide Shop*, or *Booster Packs*, as well as those contained in the *HyperScreen* library. Select <None> next to "Effect:" in the Button Info box. The Stack Disk Menu box will appear.



Select the Sound folder. This Sound folder is divided into three folders: Music, Sound.Effects, and Speech.



Select the folder that you want to open. Then select the file that you want to hear. When you make a selection, you will hear the sound clip and the Sound/FX menu will appear on your screen:



At this point, you can:

- Select Play Sound/FX to hear the sound clip again.
- Select Remove Sound/FX to remove the sound from your screen and return to the Button Info box.
- Select Change Sound/FX to return to the Disk Menu box where you can select a different sound clip.
- Press Esc or click outside the Sound/FX menu to keep the sound clip and return to the Button Info box.

For example, if you selected the music called Bach.Intro from the Disk Menu box, above, this Button Info box would appear.

Info: Button 1

Type: Sound/FX

☒ Clickable

☐ Do On Opening

Effect: BACH INTRO

Press Esc to accept.

Press Esc to accept the button information and return to your current screen.

NOTE: You can only have one sound clip saved per screen, so all Sound/FX buttons on one screen will play the same sound. This also means that changing the sound for one Sound/FX button changes the sound for all Sound/FX buttons.

Text Entry A Text Entry button, when clicked, opens up a response area (that can extend a screen width) for your user to type a response and then links to one of two screens depending on the answer. You can set a range of answers by entering a pattern that will be matched to the user's response (match pattern) according to the guidelines on page 69.

When you select this button type from the Button Type menu (see Choosing a Button Type, page 57), the Button Info box that appears will look like this.

Info: Button 1

Type: Text Entry

☒ Clickable

☐ Do On Opening

Match: <None>

If Yes: <None>

If No: <None>

Set Entry Blank

Press Esc to accept.

NOTE: In the Button Info box, use the Tab key or the arrow keys on the keyboard to move the outlined box over the information or option you wish to change, and then press Return. Another method is to point to the information or option with your pointer device and click.

To enter a match pattern (the range of responses considered correct) for your Text Entry button, select <None> beside "Match:" in the Button Info box. The Match Pattern box will appear.

Match Pattern

|

Ex: letters_or_1word

Press Esc to accept.

You can enter up to four lines of 22 characters on each line. To enter your match pattern, follow these guidelines:


- The program treats upper and lower-case letter as the same, so that "Pattern" or "pattern" will be considered the same response.
- If you simply type a string of characters as the match pattern, such as a word or group of letters, the user's answer will be considered correct if those characters can be found anywhere within the response. For instance, if you type **plan** as your match pattern, both "airplane" or "ivy plant" would match the pattern.
- If you want only an exact word to match, put vertical bars around it in the Match Pattern box. For instance if you want only "plan" to match, type **[plan]** in the Match Pattern box. When you enter a match pattern with vertical bars around it in this way, your user will need to have a non-letter or non-numeral character such as a space or punctuation mark around the typed answer for it to match exactly.
- If you want to allow for variable spellings in the response, use "@" as a wildcard character that will match to any letter or numeral typed in that spot. For instance, if you type **l@tter** as your match pattern, your user could type **letter**, **latter**, or **litter** in the Text Entry box and the answer would match.
- If you want to allow for a variety of answers to match, type **_or_** between possible answers in the Match Pattern box. For instance, if you are asking for the sum of 2 and 2, you could type in the match pattern as **4_or_four**. You can put in as many possible answers between **_or_** as will fit in the Match Pattern box. If your user types any one of the possible answers, it will match.

- If you want to allow for a two-part answer that could be in a varying order or with intervening words, use _and_ between parts or words of your answer. For instance, "T_and_Edison" would match the answers T.Edison, Thomas Edison, or Thomas Alva Edison typed in the Text Entry box.


NOTE: You can't mix _and_ and _or_ in the same match pattern.

Press Esc to accept your entered Match Pattern. A portion will appear in the Button Info box.


To select the screen that will open for a match, select <None> beside "If Yes:" in the Button Info box. The Yes Match Screen menu will appear.




You can link a correct response to a new screen, an already named screen, the previous screen, or Stack End. (See the section on choosing a linking screen, page 59.) After you choose the screen that will open for a correct response, the screen name will appear in the Button Info box.




To select the screen that will open for a wrong (non-matching) answer, select <None> beside "If No:" in the Button Info box. The No Match Screen menu will appear.



You can link an incorrect (non-matching) response to a new screen, an already named screen, the previous screen, or Stack End. (See the section on choosing a linking screen, page 59.) After you choose the screen that will open for a non-matching response, the screen name will appear in the Button Info box.



To make the entry blank the area where the user can type a response, select Set Entry Blank from the Button Info box. Your screen will appear with a text-line high cursor box at the top of the Text Entry button.




You can position and resize the entry blank just as you do a button. The position and size of the entry blank is independent of the text entry button. (See the section on resizing and moving a button, page 54.) Click inside the entry blank and drag it to your desired location. Make sure that the length of your Text Entry box will accommodate the amount of text your match requires. Pull from the handle to resize. If you pull it to a size higher than a text line, it will spring back to a text-line high size. You can extend the entry blank up to a screen width.

Once you've set your entry blank to your desired size and location, press Esc to return to the Button Info box. Then press Esc to accept the button information.

REMEMBER: You can change any of the information in the Button Info box by clicking that option or name, or by moving the outlined box over the option and pressing Return.


If you click on a Text Entry button while browsing, as in this sample, the cursor will appear in the location you set.




Your user will type in the text and press Return to enter it.

Video Control A Video Control button, when clicked, controls an attached Pioneer LD-V4200 videodisc player. Using the special letter and number codes listed on page 141, you enter a series of commands to control the player. There are 27 commands you can use, along with two special *HyperScreen* commands. For instance, by clicking a button, you could start up and display a series of four still images, with a ten-second wait in between. Or you could show a video clip twice, once at normal speed and then in slow motion. With the Apple Video Overlay card, you can use the Video Control button to show both Video images and *HyperScreen* graphics and buttons on the same screen. See Appendix A for a detailed list of commands, a glossary of terms, and a description of equipment you will need.

When you select this button type from the Button Type menu (see instructions for Choosing a Button Type, page 57), this Button Info box will appear.




Select <None> next to "Port:" in the Button Info box. The Video Control Port menu will appear.



Choose the port/slot that your videodisc is connected to, such as the modem port.


To enter your videodisc command, select <None> next to "Command:" in the Button Info box. The Video command box will appear. Type in your videodisc commands. Each line typed in the box can be up to 20 characters long and must end with a Return. You may use upper- or lowercase letters.



See Appendix A for a detailed list of commands and their uses.

The TOOLS MENU

The TOOLS MENU is divided into three sections.



- The first section contains items that are available for both Graphic and Text screens.
- The second section, between the dotted lines, contains tools that are available only when creating a Graphic screen.
- The third section contains the Text Editor and Import Text features, only available when creating a Text screen.


At any point in the program, the available tools will appear in boldface.

When working with the graphic tools, you can use the OPTIONS MENU to set the graphic font, brush shape, line width, or ink color. (See OPTIONS MENU, page 93, for a full description of these menu items.) You can also call up the graphic font, brush shape, line width, and ink color submenus by pressing control keys as you work without having to escape and return to the OPTIONS MENU each time. When you choose a graphic or text tool, the menu bar will disappear, leaving you the full screen for designing. To make the menu bar reappear, either press Esc, or move your pointer into the upper right-hand corner of the screen and leave it there for several seconds. Press Esc again to return to the point from which you escaped and continue working.

Border

Select Border to add a decorative frame to a Text or Graphic screen. You will have a variety of borders to choose from.

When you select Border from the TOOLS MENU, the last used border or the default border (Classic) will automatically be drawn around your screen and the menu bar will disappear. The Border box will appear in the center of your screen with the title Classic at the top.



To erase the Border and return to the screen with the TOOLS MENU open, select Remove Border from the Border box. Press Return or click.

To select a different border:

1. Insert a disk containing borders, such as Disk B, Side 2 into a disk drive.
2. Select Change Border from the Border box. Move the outlined box to Change Border and press Return or click Change Border.
3. The Disk Menu box will appear listing the available folders. Select the Borders folder.
4. A list of files in the Borders folder will appear in the window. Select the border you want. To preview the borders, see Appendix B.
5. When you are satisfied with the border you selected, press Esc or click anywhere outside the Border menu to return to the screen with the TOOLS MENU open.

A check mark (✓) will appear next to the Border item indicating that you've added a border to this screen.

To change the color of your border, see Border Color, page 95.


To restore the original border after you've made changes using the graphic tools, select Redraw Border and the program will fix the border.

NOTE: If you used Flood Fill to fill your screen with a color and the color seeped into the border area, select Redraw Border. The original border will reappear on the screen.

Opening Transition

Select this item from the TOOLS MENU to choose a visual effect for your screen when it first appears on the screen. *HyperScreen* provides 15 different opening transitions. For example, use Venetian Blind to make the screen appear in strips as if a venetian blind is being opened. Or use Checker Jumble to make the screen appear in squares like a checkerboard.

After you select Opening Transition, the Opening Transition menu will appear:



To choose a transition:

Keyboard: Use the Up or Down arrow key to scroll through the list of opening transitions. When the transition you want is highlighted, press Return.

Joystick or mouse: Click the arrows on the right of the Opening Transition menu to scroll through the list of transitions. When you see the transition you want, point to it and click the Action button.

That transition will be demonstrated on the screen. To see the transition again, select Preview Screen from the FILE MENU.

When you return to the TOOLS MENU, a check mark (✓) will appear next to Opening Transition indicating that you have added a transition to this screen.

If you do not select an opening transition for a screen, the program will automatically "cut" to the next screen. This means that the next screen will replace the current screen.

IMPORTANT: If you add to or change a screen you have saved, you must save the screen again. For example, if you save a screen and then add an opening transition, you will need to save your screen again to keep that transition.

Graphic Tools

Use the 11 graphic tools to create text and artwork on your Graphic screen.

- Use Brush, Pen Line, Frame, Block, Ring, and Oval to draw your own art.

NOTE: When using the keyboard to draw, the Apple key works the same as the Action button on the joystick, mouse, or touchpad. You must hold down the Apple key as you draw with the arrow keys, and press it to stamp clip art on the screen.

- Use Flood Fill to color original and *HyperScreen* art.
- Use Type to write using graphic fonts.
- Use Clip Art and Graphic Background to select from a variety of *HyperScreen* clip art and graphic backgrounds. You can use clip art and backgrounds from *Slide Shop*, *Super Story Tree*, and *Scholastic Booster Packs*. You can also use any clip art compatible with *The Print Shop*.

Brush


Select Brush to draw freehand designs in a variety of colors and patterns. The color of the brush will be determined by the ink color you have selected from the OPTIONS MENU. This color appears in the small box on the far right of the menu bar. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

When you select Brush, the menu bar will disappear and a brush shape will appear on your screen, ready for you to begin drawing.

If you have not selected or changed brush shapes from the OPTIONS MENU, your brush will appear in the large square shape. You can change your brush shape at any time as you work in one of these two ways:

1. Press Esc to bring the menu bar into view. Open the OPTIONS MENU and select Brush Shape. The Brush Shape submenu will appear. Select your brush shape. (See instructions on page 96 for using the submenu.) Press Esc again once the OPTIONS MENU reappears to return to your screen. You will see your new brush shape on the screen.

2. Press Ctrl-S and the Brush Shape submenu will appear.



Select one of these brush shapes. The submenu will be cleared from the screen, and your cursor will appear in the brush shape you have selected.

To draw, follow these steps:

1. Move your cursor to the point on the screen where you want to begin drawing.
 2. Press and hold down the Apple key (keyboard) or the Action button (joystick or mouse) as you move the cursor. The "ink" will follow the movement of the cursor.
- NOTE: If you are using the keyboard, you can toggle between fast and slow cursor movement by pressing the Space Bar.*
3. To stop drawing, release the Apple key or Action button.
 4. To continue drawing somewhere else on the screen, repeat Steps 1 and 2.
 5. To undo the last line drawn, press Ctrl-Z.
 6. To select a different brush shape press Ctrl-S to call up the Brush Shape submenu, or, press Esc to return to the menu bar. Open the OPTIONS MENU and select Brush Shape. Then select a new shape from the Brush Shape submenu.
 7. To stop drawing and return to the menu bar, press Esc (keyboard) or move your pointer (joystick or mouse) to the extreme upper right-hand corner of your screen.

HINT: The Brush tool is an excellent way to erase mistakes from your Graphic screens. First select the ink color that matches your background color. Then use the Brush to cover (erase) your error. If the area you want to cover is small or oddly shaped, be sure to select the Brush Shape that will most easily cover your mistake without destroying any work you want to leave intact.

You can use these control keys as you draw with the Brush tool:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-S to change the brush shape.
3. Press Ctrl-Z to undo the last thing drawn.

Pen Line


Select Pen Line to draw straight lines in five different widths.

The color of the line will be determined by the ink color you have selected from the OPTIONS MENU. This color appears in the small box on the far right of the menu bar. (See Ink Color, page 93.) Press Ctrl-I or Tab to change the ink color while using this tool without escaping to the OPTIONS MENU. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

When you select Pen Line, the menu bar will disappear and a cursor in a cross-shape will appear on your screen, ready for you to begin drawing.

If you have not selected or changed pen width from the OPTIONS MENU, your line will appear in the narrowest width. You can change your pen width at any time as you work in one of these two ways:

1. Press Esc to bring the menu bar into view. Open the OPTIONS MENU and select Pen Width. The Pen Width submenu will appear. Select your pen width. (See instructions on page 96 for using the submenu.) Press Esc again once the OPTIONS MENU reappears to return to your screen. You can begin using the new pen width on the screen at the point you escaped from.
2. Press Ctrl-W and the Pen Width submenu will appear.



Select one of the pen widths. The submenu will be cleared from the screen, and your cursor will reappear. You can begin drawing in your new pen width.

To draw a line, follow these steps:

1. Move your cursor to the point on your screen where you want the line to begin.
2. Press and hold down the Apple key (keyboard) or Action button (joystick or mouse) as you move the cursor. A line will follow the movement of the cursor.
3. When the line is the correct length and in the proper position, release the Apple key or Action button and the program will redraw the line in the current link color.
4. To draw a line somewhere else on the screen, repeat Steps 1 and 2.
5. To undo the last line drawn, press Ctrl-Z.
6. To select a different pen width, press Ctrl-W as you work to call up the Pen Width submenu, or press Esc to return to the menu bar. Open the OPTIONS MENU and select Pen Width. Then select a new width from the Pen Width submenu.
7. To stop drawing and return to the menu bar, press Esc (keyboard) or move your pointer (joystick or mouse) to the extreme upper right-hand corner of your screen.

HINT: If you want to draw a series of connected straight lines, use the endpoint of one line as the beginning point of the connecting line. Just remember to release the Apple key or Action button to complete one line before you begin another line.

You can use these control keys as you draw with the Pen Line tool:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-W to change the pen width.
3. Press Ctrl-Z to undo the last line drawn.

Frame

Select Frame to draw rectangular and square box outlines.

The color of the line will be determined by the ink color you have selected from the OPTIONS MENU. This color appears on in the small box on the far right of the menu bar. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

When you select Frame, the menu bar will disappear and a cursor in a cross-shape will appear on your screen, ready for you to begin drawing.

If you have not selected or changed pen width from the OPTIONS MENU, your frame will appear in narrowest line width. You can change your pen width at any time when you work in one of these two ways:

1. Press Esc to bring the menu bar into view. Open the OPTIONS MENU and select Pen Width. The Pen Width submenu will appear. Select your pen width. Press Esc again once the OPTIONS MENU reappears to return to your screen. You can begin using the new pen width on the screen at the point you escaped from.

2. Press Ctrl-W and the Pen Width submenu will appear. Select one of the pen widths. The submenu will be cleared from the screen and your cursor will reappear. You can begin drawing in your new pen width.

Follow these instructions to create a frame:

1. Place the cursor at one corner of the frame and hold down the Apple key (keyboard) or Action button (joystick or mouse).
2. Continue holding down the Apple key or Action button, and press the Arrow keys or move your pointing device to stretch the "rubber band" frame in the direction that you want the frame to appear. As you move around the screen, a rectangle will follow the movement.
3. When you've created the frame with the proportions you want, release the Apple key or Action button and the program will redraw the frame in the current ink color.
4. To draw a frame somewhere else on the screen, repeat Steps 1 and 2.
5. To undo the last frame drawn, press Ctrl-Z.
6. To select a different pen width, press Ctrl-W as you work to call up the Pen Width submenu, or press Esc to return to the menu bar. Open the OPTIONS MENU and select Pen Width. Then select a new width from the Pen Width submenu.
7. To stop drawing and return to the menu bar, press Esc (keyboard) or move your pointer (joystick or mouse) to the extreme upper right-hand corner of your screen.

You can use these control keys as you draw with the Frame tool:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-W to change the pen width.
3. Press Ctrl-Z to undo the last line drawn.

Block

Select Block to create solid squares and rectangles.

The color of the block will be determined by the ink color you have selected from the OPTIONS MENU. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

NOTE: Blocks differ from frames in that frames are empty while blocks are filled with a color.

To create a block:

1. Select Block from the TOOLS MENU. Place the cursor at one corner of the block and hold down the Apple key (keyboard) or Action button (joystick or mouse).

2. Continue holding down the Apple key or Action button and press the arrow keys or move your pointing device to stretch the rubber band block in the direction that you want the block to appear. As you move around the screen, the block will follow the movement.
3. When you've created a block with the proper proportions, release the Apple key or Action button and the program will redraw the block in the current ink color.
4. To see the menu bar, press Esc or move the cursor to the upper right-hand corner of the screen.

The Block tool is also handy when you want to create a text window. For example, to add text to a colored area of a graphic background, you can place a white block where you want the text to appear. Then type inside the block using a different color ink.

You can use these control keys as you draw with the Block tool:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-Z to undo the last block drawn.

Ring

Select Ring to draw circular or oval lines in a variety of line widths.

The color of the ring will be determined by the ink color you have selected from the OPTIONS MENU. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

When you select Ring, the menu bar will disappear and a cursor in a cross-shape will appear on your screen, ready for you to begin drawing.

If you have not selected or changed pen width from the OPTIONS MENU, your ring will appear in the narrowest line width. You can change your pen width at any time when you work in one of these two ways:

1. Press Esc to bring the menu bar into view. Open the OPTIONS MENU and select Pen Width. The Pen Width submenu will appear. Select your pen width. (See instructions on page 96 for using the submenu.) Press Esc again once the OPTIONS MENU reappears to return to your screen. You can begin using the new pen width on the screen at the point you escaped from.
2. Press Ctrl-W and the Pen Width submenu will appear. Select one of the pen widths. The submenu will be cleared from the screen, and your cursor will reappear. You can begin drawing in your new pen width.

To draw a ring:

1. Place the cursor at the screen location where you want the ring to begin and press the Apple key (keyboard) or Action button (joystick or mouse).

2. Hold down the Apple key or Action button and use the arrow keys or move the mouse or joystick to begin drawing the ring. When you draw up or down, the ring will become tall and narrow. Moving sideways will make short and wide rings. To draw circles, move diagonally from the starting point.
3. When the ring is the size and shape you want, release the Apple key or Action button.
4. To draw a ring somewhere else on the screen, repeat Steps 1 and 2.
5. To undo the last line drawn, press Ctrl-Z.
6. To select a different pen width, press Ctrl-W as you work to call up the Pen Width submenu, or press Esc to return to the menu bar. Open the OPTIONS MENU and select Pen Width. Then select a new width from the Pen Width submenu.
7. To stop drawing and return to the menu bar, press Esc (keyboard) or move your pointer (joystick or mouse) to the extreme upper right-hand corner of your screen.

You can use these control keys as you draw with the Ring tool:

1. Press Ctrl-I to change the ink color.
2. Press Ctrl-W to change the pen width.
3. Press Ctrl-Z to undo the last line drawn.

Oval

Use the Oval item to create solid circles and ovals.

The color of the oval will be determined by the ink color you have selected from the OPTIONS MENU. This color appears in the small box on the far right of the menu bar. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I. The ink color palette will appear and you can select your color and continue drawing. (See page 94 for a complete description of the ink color palette.)

Follow these steps to draw a solid oval:

1. Select Oval from the TOOLS MENU.
2. Place the cursor at the screen location where you want the oval to begin and press the Apple key (keyboard) or Action button (joystick or mouse).
3. Hold down the Apple key or Action button and use the Arrow keys or move the joystick or mouse to begin drawing the oval. When you draw up or down, the oval will become tall and narrow. Moving sideways will make short and wide ovals. To draw circles, move diagonally from the starting point.
4. When the oval is the size and shape you want, release the Apple key or Action button.

You can use these control keys as you draw with the Oval tool:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-Z to undo the last line drawn.

Flood Fill

Use Flood Fill to fill black or white areas of the screen with color.

The flood fill color is the ink color you have selected from the OPTIONS MENU. This color appears in the small box on the far right of the menu bar. (See Ink Color, page 93.) You can change the ink color while using this tool without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue flood filling. (See page 94 for a complete description of the ink color palette.)

Here is how it works:

- 1. Select Flood Fill from the TOOLS MENU.
- 2. Place the cursor inside the black or white area you want to fill.
- 3. Press the Apple key (keyboard) or Action button (joystick or mouse) to fill the area.

IMPORTANT: Flood Fill will leak out of an area that is not completely enclosed. It works only on black or white areas.


If you want to fill a small area, your cursor must be located inside the area you want to fill. If your cursor overlaps the outline of the area, you will get an error message. The program thinks you are trying to fill a pattern, rather than a solid black or white area. Press Return or click OK. Then try again and make sure your cursor is completely within the area that you want to fill.

You can use these control keys as you use Flood Fill:

- 1. Press Ctrl-I or Tab to change the ink color.
- 2. Press Ctrl-Z to undo the last Flood Fill.

Type

Use Type to add text to your Graphic screens in any of the following type fonts:




To select a color for your text, see Ink Color, page 93. You can change the ink color while typing without escaping to the OPTIONS MENU by pressing Ctrl-I or Tab. The ink color palette will appear and you can select your color and continue typing. Follow these instructions to add text to your Graphics screen:

- 1. Select Type from the TOOLS MENU. A cursor will appear on the screen. Unless you have changed the graphic font, your text will appear in the System 8 font.
- 2. Before you begin typing, move the cursor to the point on your screen where you want to set your left margin and press the Apple key (keyboard) or Action button (joystick or mouse). To reset your margin, press Esc, move your cursor to a new position, and press the Apple key or Action button.
- 3. Type your text. Text normally appears on a transparent background. If you want a white background surrounding the text, press Ctrl-B before you begin typing. Press Ctrl-B again to create a transparent background again.

You can combine different fonts on a single Graphic screen. To change fonts, use either of these methods:

- 1. Press Esc to return to the menu bar and open the OPTIONS MENU. Then select Graphic Font. Follow the instructions for using the submenu below or see page 97. When you have selected your font, you will return to the OPTIONS MENU. Press Esc to return to your current screen at the point you escaped.
- 2. Press Ctrl-F. The Type Font submenu will appear on your screen:



The System 8 and Orpheum 12 fonts are stored on the HyperScreen program disk. If you select either of these fonts, the Type Font submenu will disappear and you will be ready to begin typing.

If you want to use a different font, insert Side 2 of HyperScreen Disk B or a disk with compatible fonts into a drive and select Font From Disk. The Disk Menu box will appear on your screen. Select the Fonts folder. Then select the font you want to use.

When you call up the Type Font submenu, if you had previously selected a font from the disk, you'll notice the font you selected has replaced Orpheum 12 on the Type Font submenu. You can select one of these fonts, or you can choose the Font From Disk option to select another font from the Fonts folder.

You can use these control keys as you type:

1. Press Ctrl-I or Tab to change the ink color.
2. Press Ctrl-F to change the pen width.
3. Press Ctrl-B to alternate between a transparent and opaque white background.

Clip Art

Select Clip Art to load clip art onto your screen. The *HyperScreen* package includes an assortment of clip art to enhance your creations. You can also use *Slide Shop*, *Super Story Tree*, *Scholastic Booster Packs*, or any of the *The Print Shop* compatible clip art with the *HyperScreen* program. In addition, you can create and save your own full-color clip art.

Using the Clip Art Libraries

HyperScreen, *Super Story Tree*, *Scholastic Booster Packs*, *Slide Shop*, and *The Print Shop* compatible clip art appears as a blank outline image on your screen. This means that the "inside" of the clip art will be the same color as the background on which you place it. To color your clip art, stamp it on a white background. Then use the Flood Fill tool to fill areas of the clip art with color. (See Flood Fill, page 84.)

HINT: If you have a screen with a colored background, and you want to add and color clip art, press Ctrl-B to create an opaque white background for the clip art. Later, you can use the Flood Fill tool to color the clip art and the surrounding white areas. Press Ctrl-B again and the clip art will appear in inverse. That is, the clip art background will remain transparent, but the black lines will appear in the background's opposing color (for example, white on black, red on blue).

NOTE: Some of *HyperScreen*'s clip art icons contain color.


Selecting a Piece of Clip Art

To select a piece of clip art, follow these instructions.

NOTE: *HyperScreen*, *Super Story Tree*, *Slide Shop*, and *The Print Shop* clip art are handled in the same manner. You do not need to convert *The Print Shop* clip art to *ProDOS* to use it with *HyperScreen*.

1. Insert the disk containing your clip art into a disk drive. (The *HyperScreen* Clip Art Library is stored on Side 1 of Disk B.)

2. Select the Clip Art item from the TOOLS MENU. The Disk Menu box will appear on your screen.



3. The *HyperScreen* clip art is stored in folders that contain groups of related clip art. Select the folder that you want to open. (To preview the clip art in each folder, see Appendix B.) To close a new folder, press the \ key (keyboard) or click Close (joystick or mouse). Then select the folder you want. A list of the clip art files in that folder will appear in the menu window.
4. Select a clip art file. That clip art will appear on your screen. If you are not satisfied with your selection, press Esc to return to the Disk Menu box where you can select another piece of clip art.
5. Move the clip art by using the arrow keys or pointing device. You can flip it horizontally by pressing H or vertically by pressing V. Press the H or V key again to flip the clip art back to its original position.

HINT: If you have a screen with a colored background and you want to add and color clip art, press Ctrl-B to create an opaque white background for the clip art. Then use the Flood Fill tool to color the clip art and the surrounding white areas. Press Ctrl-B again and the clip art will appear in inverse, i.e., the clip art background will remain transparent, but the black lines will appear in the background's opposing color (for example, white on black, red on blue).

6. Stamp the clip art on the screen by pressing the Apple key or Action button.

You can stamp the clip art as frequently as you like on a single screen. When you have finished stamping clip art, press Esc. The last piece of clip art you selected will be temporarily stored in the clipboard used by the Paste item. (See Paste, page 52.)

Coloring Your Clip Art

The easiest way to color your clip art is to use the Flood Fill item. Since you can only fill white or black areas, you should stamp your clip art on a white background before adding background color to your screen.

You can also use *HyperScreen's* drawing tools to color or embellish clip art, although this technique requires more time and drawing skill than using the Flood Fill tool.

Graphic Background

Select this item to load background art onto your screen. *HyperScreen* includes an assortment of graphic backgrounds which you can use to enhance your screen. Graphic Backgrounds are stored on Side 1 of Disk B.

Graphic Backgrounds are specially designed full-screen backgrounds that often include blank space where you can draw, add text, or clip art.

The collection of *HyperScreen* graphic backgrounds on your disk are shown in Appendix B. You can also use the wide array of graphic backgrounds from *Slide Shop*, *Super Story Tree*, or *Scholastic Booster Packs*.

To select a graphic background, follow these instructions:

1. Insert the Graphic Background disk in a drive (Disk B, Side 1 or another disk containing the graphic background you want).
2. Select Graphic Background from the TOOLS MENU.

NOTE: If you select a graphic background and there are already graphics or text on the screen, the program will warn you that you are about to erase the screen if you have not already saved it. If you don't want to erase what is on the screen, press Esc or click Cancel.

3. The Disk Menu box will appear on your screen. Select the file you want to open.
4. The Disk Menu box will disappear and the background you selected will fill the screen.
5. Press Esc. The Disk Menu box will appear on your screen. You can select another background. When you're satisfied with your selection, press Esc or click Cancel to keep the background and return to the menu bar.

To remove the background from the screen, select Clear from the EDIT MENU.

Select Graphic Background when you want to use full-screen graphics that were created with compatible paint programs. You can also use this feature to import screens from your *Slide Shop* shows or pages from *Super Story Tree*.

Using *HyperScreen* with Other Graphics Programs and Utilities

Graphics created with any paint program that supports standard single hi-res graphics for the Apple can be used with *HyperScreen* and easily incorporated into your screen presentations. This includes both ProDOS and DOS 3.3 graphics programs such as *816 Paint™*, *MousePaint™*, *Stickybear® Draw*, *Blazing Paddles™*, *Graphics Magician™*, and many more. You can even use Logo screens stored as single hi-res graphics. You can also use any video digitizing system that saves images as single hi-res graphics, for example, *Computer Eyes™* or *Thunderscan®*, to create images for your stories.

HyperScreen also contains a special save feature which allows you to export *HyperScreen* graphics to other paint programs in case you need to use more specialized paint programs. However, you can export *HyperScreen* images directly only to compatible ProDOS programs such as *816 Paint*. You will need to convert your *HyperScreen* graphics for use with DOS 3.3 programs. (See Export Screen Image, page 48.)

Using *SuperPrint* Clip Art with *HyperScreen*

To use *SuperPrint* Clip Art with *HyperScreen*, you will first need to convert the graphics using the *Pelican Graphics Converter™* program. The *Pelican Graphics Converter* is available as a separate Scholastic product (product number 86348). To order, call 800-541-5513. In Missouri, call 800-392-2179.

Text Tools

Use the Text Editor and Import Text features of the TOOLS MENU to design your text screens. Special keys work on text pages to form a rounded box for your buttons and to place arrows on your screen (see page 91).


Text Editor

Select Text Editor from the TOOLS MENU to use *HyperScreen's* built-in word processor. You can add text to your Text screens in a variety of fonts.

NOTE: To add text to a Graphic screen, choose the Type option from the TOOLS MENU.

To enter text, use the Space Bar and the Return key to position your cursor. Then begin typing.

To change text fonts, Press escape to return to the menu bar. Select Text Font from the OPTIONS MENU. (See Text Font, page 98.) The Text Fonts submenu will appear on the screen.



NOTE: You can use one text font per screen. You can, however, change fonts at any time. When you select a new font, any text on your screen will change to the new font.

After you select a font, you will have the full screen to type your text.

The vertical cursor bar indicates that you are in the Insert typing mode. In the Insert mode, when you move the cursor into a block of text, all the text to the right of the cursor moves right when you insert text and moves left when you delete text.

To toggle between the Insert and Typeover modes, press Ctrl-E. In the Typeover mode, when you move the cursor into a block of text and begin typing, the new text will cover, or "typeover," the old text. The horizontal underline cursor indicates that you are in Typeover mode.

The following editing commands are available when you are using the Text Editor:

Use:	To:
Arrow Keys	Move the cursor up, down, left, and right
Delete, Ctrl-D	Delete backward, erasing the character to the cursor's left
Ctrl-F	Delete forward, erasing character to cursor's right
Ctrl-X	Clear text; erase all characters
Ctrl-Z	Undo editing; restore original text
Ctrl-E	Toggle between Insert and Typeover typing modes
Esc	Finish editing, and return to the menu bar

NOTE: You can substitute the Apple key for the Control key in each Control key combination above.


You can use the Text Editor with any color in the *HyperScreen* Color Palette. (See Ink Color, page 93.) However, you can use only one ink color on a single Text screen. If you change ink colors at any point in the design of your Text screen, all text on the screen will appear in the new color you have selected. You can also choose different background colors for your Text screens. (See Text Background, page 98.)

Special Feature: A Rounded-corner Button Box

You can make a special box on your text screen to design buttons. This comes in handy for enclosing prompts and putting buttons on your screens. Here's a list of the eight keys you'll use to do this.

Press:	To create this section:
{ (Shift-[)	top left corner ({)
[bottom left corner ([)
} (Shift-])	top right corner (})
]	bottom right corner (])
\	top or bottom line of box (-)
(Shift-\)	right or left side of box ()

A button box might look something like this:



Special Feature: Screen Arrows

You can create arrows on your screen with special keys, especially useful in designing buttons on your text screens.

Press ``` for a right arrow (`→`)

Press `~` (Shift `'`) for a left arrow (`←`)


Import Text

With the Import Text feature of the TOOLS MENU, you can import text from compatible word processors, *Super Story Tree* text pages, or *Slide Shop* text slides to your HyperScreen screens.

The file of text you can import can be of type BIN or TXT on DOS 3.3 or ProDOS disks.

Imported text appears in the font and color you are currently using. You can't import special formatting codes, such as tabs or centering, in the text.


When you select Import Text, the Disk Menu box appears.



Select the file of text you want to import.

The OPTIONS MENU

The OPTIONS MENU allows you to set a number of options for Text and Graphic screens before you use the graphic or text tools. The OPTIONS MENU is divided into four sections.




- The first section contains items to set for both Graphic and Text screens, including ink, border, and video key color (the color that will indicate where a video image will show through on the screen when overlaying computer graphics and video).
- The second section, between the dotted lines, contains items to set only when creating a Graphic screen.
- The third section contains items to set for Text screens.
- The fourth section contains the item for setting Browse Options.

Ink Color

Select this option to choose the color that appears on your screen when you use the Brush, Pen Line, Frame, Block, Ring, Oval, Flood Fill, Type, and Text Editor tools. The current ink color is displayed in the small box on the upper right-hand side of the menu bar.

Selecting an Ink Color

Each time you load the *HyperScreen* program, the ink color will be set to black until you select a new color. To change colors, open the OPTIONS MENU and select the Ink Color option. The *HyperScreen* Color Palette will appear on your screen.



The current color will be enclosed in a black frame. It will also appear in the large rectangle at the top of the palette.

To select a new color, use the arrow keys or the pointer to move the cursor box over the color you want, and then press Return or click the Action button.

After you choose a color, the palette will close and you will return to the menu bar. Notice that the color you chose will now appear in the color window on the upper right-hand side of the menu bar.

NOTE: When working with a Text screen, selecting a different ink color will change the color of all text that is currently on the screen.

The *HyperScreen* Color Palette

Because of the way Apple computers display colors, certain colors from the palette will "clash." This means when they are placed side by side, pixels of one color will cause pixels of a clashing group to change color.

The *HyperScreen* Color Palette is designed to minimize clashing and to give you the maximum number of color choices. Row 1 of the palette consists of colors that can be used together without clashing. Similarly, Row 2 of the palette consists of colors that can be used together without clashing. However, if you place a color from Row 1 directly beside a color from Row 2, clashing will occur.

You'll notice that Rows 1 and 2 both contain black and white. While these colors look identical, they will react differently on your screen. To avoid clashing, choose the black or white from the row of colors you are working in. For example, if you want to type black letters on a background color from Row 2, choose the black from Row 2.

HINT: Mixing blacks or whites from Rows 1 and 2 will not cause clashing.

The colors in Rows 3 through 10 have been created by mixing colors from Rows 1 and 2. Any of these colors can be used together without clashing. For example, you can use a blue from Row 6 with a green from Row 9 without clashing.

There may be a degree of clashing when placing colors from Rows 3 through 10 adjacent to the colors from Rows 1 and 2.

NOTE: All colors can be used on the same screen. Clashing occurs only when colors from Rows 1 and 2 are placed side-by-side or on top of each other (for example, placing colored text from Row 1 on a background color from Row 2).

Border Color

Select this option to select a color for your Text or Graphic screen border. You will change the black border design to the color you chose, while the border background will remain white. If you are working on a Graphic screen, you can use the Flood Fill option or one of the other drawing tools to color in the white.

To change border color, when the color palette appears, select the new color for your border color.


NOTE: Changing the border colors will sometimes change the design of your border. If this happens and you do not like how it looks, select Undo from the EDIT MENU. If it is too late to undo the color, select Border Color again. Then select Black from the Color Palette. Your border will return to black.

Once you select a border color, all subsequent borders you select will appear in that color until you select a different border color or quit the program.

Video Key Color

This option works with a Video Overlay Card on your computer. With the Video Key Color option you can create exciting mixes of text, computer graphics, and video on a single screen. When you select a key color, everything on your computer screen in that color will appear transparent, and the Video image will show through.

When you select Video Key Color, the Video Key Color options menu will appear.




You can select from six high-resolution colors. Select None if you don't wish to show any video. Select All if you wish to show only the video and not the computer screen.

Brush Shape

Select this item to choose from a set of 32 brush shapes, before using the Brush, or to change the brush shape while drawing.

The Brush Shape submenu will appear.




Click your selection, or move the outlined box over your selection with the Tab or arrow keys, then press Return. When you select Brush from the TOOLS MENU, your brush will appear in your selected shape.

REMINDER: You can press Ctrl-S to select from the Brush Shape submenu while using the Brush without escaping to the menu bar and opening the OPTIONS MENU.

Pen Width

Select this item to choose from a set of five pen widths before using the Pen Line, Ring, or Frame, or to change the pen width while drawing.

The Pen Width submenu will appear.




Click your selection, or move the outlined box over your selection with the Tab or arrow keys, then press Return. When you select Pen Line, Ring, or Frame from the TOOLS MENU, your pen will draw in your selected width.

REMINDER: You can press Ctrl-W to select from the Pen Width submenu while using the Brush without using OPTIONS MENU.

Graphic Font

Select Graphic Font to change fonts before typing on your Graphic screens, or during typing. When you select Graphic font, the Type Font box will appear.




Select System 8 or Orpheum 12.

To use a different font, insert Side 2 of Disk B (or a *Super Story Tree* or *Slide Shop* disk containing the font you want) into a drive and select Font From Disk. The Disk Menu box will appear on your screen. Select the Fonts folder. Then select the font you want to use.

REMEMBER: You can change graphic fonts while typing on your Graphic screens without using the OPTIONS MENU by pressing Ctrl-F.

Text Font

Select Text Font to change fonts before or during typing on your Text screens. You can select from serif and non-serif fonts in four sizes. When you select Text Font, the Text Font menu will appear.



Select the Font you wish to use.

Text Background

Select Text Background to change the background color in the design of your Text screens. The new background color will fill the screen behind any existing text if you escape to the menu bar and change colors as you work.

NOTE: The Text Background option is available only when you are creating Text screens. It is not available for Graphics screens.


When you select Text Background, the color palette will appear on your screen. Select the color you want. That color will fill the screen behind any existing text.

If the text color clashes with the background color, the background directly behind the text will be a color other than the background color you selected. If you do not like this effect, select new colors that are compatible. (For more information, see the HyperScreen Color Palette, page 94.)

HINT: To obtain the highest resolution and most legible screens, select either black type on a white background or white type on a black background.

Browse Options

Select Browse Options to preset the options for your creation while it is being browsed through. When you select Browse Options, this Browse Options box will appear.



Darken the circle by moving the outlined box and pressing Return or clicking the option you choose.

You can choose to turn sound on or off.

If you choose to show buttons, clickable buttons will appear in an outlined box while browsing.

You can turn the Scanner feature on or off (see page 10).

Press Esc to accept the Browse Options.

REMEMBER: You can Press Esc at any time while browsing to use the complete Browse Options box, including selecting which screen to begin at.

Correcting Mistakes

There are several ways to correct mistakes on your Text and Graphic screens.

Many of the hints in the TOOLS MENU section of this Reference Guide suggest ways you can use various tools to erase errors. For example, with Graphic screens you can use the Brush tool as an eraser. Select the ink color that matches your background color. Then use the Brush tool to erase, or cover, the mistake.

You can use the Block tool to quickly cover larger areas of your screen. You may want to select a different ink color immediately after you correct your mistake to avoid confusion later. If you use a drawing tool and nothing appears on the screen, check the ink color.

In some cases, you can use the Copy tool to copy a block of your Graphic screen, then stamp that block over your mistake. This eliminates the need to change ink colors, but can only be used when you have a block of background that matches the background area you want to erase.

You can use the Cut tool to erase blocks of screen when using a white background. Remember that the cut portion will replace any contents in your clipboard.

If you are designing a Text screen, you should use the text editing commands to delete text from your Text screens. (See Text Editor, page 89.)

Finally, don't forget the Undo and Clear options on the EDIT MENU. These options make it quick and easy to correct mistakes.

PART 3: BROWSING THROUGH A *HYPERSCREEN* CREATION

Browsing Through a Stack From the Menu Bar


You can browse through a stack from *HyperScreen's* menu bar. This is useful if you want to test your stack while you are designing it to make sure it works the way you wish.

You can create a special browse mode by turning off all pointing devices. First select Pointer Setup from the APPLE MENU, and then choose the Keyboard Mouse option. In this mode, you will use the arrow keys on the keyboard to jump from button to button and make your choice. If you have no pointing device attached, this will automatically be your browse mode.

You might first want to set the Browse options, such as sound, showing buttons, and using the scanner from the Browse Options on the OPTIONS MENU. (See page 99.)


To browse:

1. Make sure the appropriate Stack disk is in the drive.
2. If you are not already working on the stack you want to browse through, choose Open Stack from the FILE MENU. Then select the stack you want to browse through from the Disk Menu box.



3. Now select Browse from the FILE MENU. You will begin browsing according to your selected Browse Options on the OPTIONS MENU. If you have not selected these, you will begin at the first screen with sound on, without buttons showing, and without the Scanner feature.

4. Press Esc while browsing to make the Browse Options box appear. Select whether you want to browse through the stack with sound, to show buttons, and select the screen from which you want to begin reading.



The darkened circles indicate the current setting. You can change these settings. You can:

- select whether you want to hear sound or not.
- select whether you want to show buttons or not. If you show buttons, they will appear in an outlined frame.
- select whether or not you want to use the Scanner. The Scanner outlines buttons one after another. You press the Space Bar or click your pointing device to select a button using the Scanner. (See Scanner, page 10.)
- select which screen you want to begin on.

TIP: Be sure to select which screen to begin at, if you wish to continue browsing. If you press Esc again or click Cancel, you will return to the menu bar and leave the browse mode.

5. Browse through the stack. Press Esc to quit the stack before the end. Pressing Esc once brings you to the Browse Options box. You can change the controls, click Cancel or press Esc to return to the menu bar.

For additional ease in browsing, you can press a single key for these functions.

Press:	To:
B	Show clickable buttons in an outline on screen. Hide the outlines by pressing again.
arrow keys	Move the pointer hand if a mouse is attached, but not if a joystick or touchpad is attached.

Move the pointer hand from one button to the next in button number order, if no pointing device is attached.

Space Bar

Toggle between one-pixel long and ten-pixel long jumps of the pointer hand across the screen, when using the arrow keys to move.


<

Back up to the last screen you viewed. You can repeat this all the way back to where you began browsing at the current stack.

Browsing Through a Stack From a Stack Disk

To browse through a stack from a self-booting Stack disk:

1. Insert the Stack disk in Drive 1 of your computer.
2. Turn on your computer and monitor. If the computer is already on, press the Control, Open Apple, and Reset keys simultaneously or select the program STACK.SYSTEM if you are using a program selector such as GS/OS
3. If more than one stack is saved on the disk, the Stack menu will appear. Select the stack you want to browse through.



4. You can press Esc at any time to use the Browse Options box or to quit browsing. When you press Esc, the Browse Options box will appear.

If you like, you can change the browse options and browse through the stack again. Be sure to select at which screen to begin, if you wish to continue browsing. To quit the stack, press Esc again or click Cancel on the Browse Options box.

TUTORIAL: HOW TO MAKE YOUR FIRST SCHOLASTIC HYPERSCREEN CREATION

HyperScreen is an interactive multimedia program with which you can create and arrange collections of information called "stacks." *HyperScreen* stacks are assembled screen-by-screen using the tools and features of the program—graphic backgrounds, clip art, drawing tools, screen transitions, text, and a variety of fonts. *HyperScreen* buttons are areas of the screen which you designate to perform certain actions when clicked. With *HyperScreen* you can create multimedia presentations, enhanced lessons, interactive stories, fact or fiction databases, information portfolios, or even administrative files.

As the author of a *HyperScreen* creation, you can design stacks for yourself or for others, building and connecting them according to your needs or the needs of the user. This tutorial will lead you through the steps of making a simple *HyperScreen* creation called "Whale Watch." This stack may be created by a teacher, student, or whale enthusiast. A few screens provide information on types of whales, and a map shows whale habitats. Pop-up text buttons display whale trivia, and there is a separate linked stack into which the stack author may enter summaries of whale books and articles. For more detailed information on the *HyperScreen* features and functions, see the Reference Guide of this User's Guide.

How Stacks Work: The Stack Design Chart

There are seven types of buttons available in *HyperScreen*:

Link to Screen Links a screen to another screen.

Link to Stack Links a screen to the first screen of a different stack, (even a stack on a different data disk).

Multi-button Initiates a chain reaction of buttons performing in a sequence you determine.

Pop-up Text Displays a box of text in the center of the screen. (You, as the author, can enter text of up to five lines in length.)


Sound/FX Plays music, speech, or a sound effect.

Text Entry Accepts text entry from the user. (You specify what text match will link the user to another screen.)

Video Control Sends a command to an attached videodisc player.

In this tutorial, you will create six of the seven button types. For more information on the Video Control button, see Appendix A.

Since *HyperScreen* offers so many possibilities for connections and movement within and outside a stack, it may be helpful for you to plan your creation on paper before you design and assemble it using the computer. If you prefer to devise your stacks as you work on the computer, charting the progress of your creation on paper can help you keep track of its design. Below is the stack design chart for the "Whale Watch" stack.



NOTE: If you are using the 3.5-inch version of *HyperScreen*, the program, all graphics, fonts, and sounds are contained on one disk. Therefore, you will not have to switch disks for this tutorial.

Loading the Program

To load the *HyperScreen* program, follow these instructions:

1. Insert the *HyperScreen* program disk (Disk A) with the label facing up (Side 1) into Drive 1 and close the disk drive door.
2. Turn on your monitor and computer. If the computer is already on, press the Control, Open Apple, and Reset keys at the same time.
3. In a few seconds the title screen will appear, followed by the Home Screen of the *HyperScreen* Home Stack.

The Home Stack is *HyperScreen*'s built-in reference guide. It provides information to help you begin using the program, and may be referred to at any time.

Once you have completed the tutorial, you can return to view the Home Stack by opening the APPLE MENU on the menu bar and selecting Home Stack. To browse through the Home Stack, select the items that interest you.

To begin this tutorial, press Esc to view the menu bar.

The *HyperScreen* Menu Bar

The Apple icon and the headings at the top of the screen comprise the *HyperScreen* menu bar. Under each heading is a pull-down menu that appears when the heading is selected. Throughout this tutorial, you will open menus on the menu bar and select items from the pull-down menus that appear. Before you begin this tutorial, be sure to select the Pointer Setup and set it accordingly. If you need help, see Part 1: Working With *HyperScreen* in the Reference Guide.

HyperScreen works with the keyboard, joystick, mouse, or touchpad. Though each works slightly differently, you can make your selections in these two basic ways:

To open a pull-down menu and select items:

Keyboard: Use the Left or Right Arrow key (← →) to highlight a menu heading at the top of the screen. The heading's pull-down menu will automatically open. To select a menu item, use the Up or Down Arrow key (↑ ↓) to highlight it. Then press Return.

Pointing Device (joystick, mouse, or touchpad): Use the pointing device to point to a menu heading at the top of the screen. Then click (press and release) the Action button on your mouse, joystick, or touchpad to open that heading's pull-down menu. To select a menu item, point to the item and click the Action button.

The Stack Disk

It is best to save your *HyperScreen* creation on a Stack disk. Stack disks are self-booting. This means you can load a Stack disk and browse through the stacks without the *HyperScreen* program disk.

If you already have a Stack disk see The Stack, below.

If you don't have a Stack disk, create one now:

1. Select Create Stack Disk from the APPLE MENU.
2. You will see a slot and disk drive selection prompt on your screen. Choose the correct drive and slot for your system. Now follow the instructions on the screen to insert a blank disk in the drive and press Return or click OK. The message, "Formatting New Stack Disk..." will appear. When the program tells you to, finish creating your Stack disk by inserting Side 2 of the program disk or a current Stack disk and pressing Return or clicking OK.

When you have finished creating a Stack disk, the menu bar will reappear.


For more information on creating a Stack disk, see page 15 in the Reference Guide.

The Stack

Your *HyperScreen* creation's basic unit is the stack, which is a collection of screens. You begin working by selecting Open Stack or starting a New Stack. For this tutorial, you will be starting a new stack. To do so, be sure your disk is in a drive and follow the steps below.

NOTE: If you have already created a Stack Disk, press Esc to view the menu bar.

1. Use the arrow keys, joystick, or mouse to open the FILE MENU.
2. Select New Stack from the FILE MENU.
3. When the Stack Menu box appears, type **WHALE WATCH** to name the new stack.



NOTE: A stack name can contain up to 13 characters.

4. Press Return or click OK to open the Home Screen of this new stack.

NOTE: The first screen of each stack is automatically called the Home Screen. It is the starting point of the stack. When you save a Home Screen, you may change this name if you wish, but calling it the Home Screen may be useful as a home base for your stack.

The Screen

Stacks are comprised of screens which you design and arrange in any way you choose. There are five basic steps involved in creating a screen. See page 19 in the Reference Guide for a full description of these steps.

The Home Screen of "Whale Watch"

Your first screen, or Home Screen, will be a title screen. You will learn the basics of creating a screen, including using a background graphic, adding clip art, and selecting a font. Then you will set one of the simplest buttons: the Link to Screen button.


Step One: Create Your Screen

HyperScreen allows you to design two kinds of screens: Text screens and Graphic screens. Text screens save space. You can type text, and use borders and color on Text screens. On Graphic screens, you can draw, add clip art, graphic backgrounds, borders, and use a wide variety of graphic fonts as well.

1. On the screen, you will now see the Text or Graphic Screen Option box:




2. Select Graphic Screen for your first screen and press Return or click on your selection. The TOOLS MENU on the menu bar will automatically open, displaying the tools available for use on a Graphic screen. Items that are not currently available will appear in dimmed type on the menu.



Step Two: Design Your Screen

Your finished screen will look like this:




Add a Graphic Background

You can enliven your screens with graphic backgrounds from *HyperScreen* Disk B, from other screens you've designed (see page 48 of the Reference Guide for instructions on using the Export Screen Image feature), from *Scholastic Graphics and Sound Booster Packs*, from *Super Story Tree*, or *Slide Shop*.

1. Insert the graphic backgrounds disk (*HyperScreen* Disk B, Side 1) in a drive. Select Graphic Background from the TOOLS MENU.

You will see the Disk Menu box:



If you need to switch drives, use the Tab key or click on the drive box.


2. Select the Backgrounds folder. A list of backgrounds will appear. Select the Clipboard background. Press Return or click OK. The graphic will appear on your screen.
3. Press Esc twice to return to the TOOLS MENU.

For more information on adding graphic backgrounds, see page 88 of the Reference Guide.


Add Text

When you add text to a Graphic screen, you can choose from one of *HyperScreen*'s various graphic fonts. To select a font, make sure *HyperScreen* Disk B, Side 2, is in a disk drive.

1. Open the OPTIONS MENU on the menu bar and select Graphic Font. The Type Font menu will appear on your screen:



2. Select Font From Disk. When the Disk Menu Box appears, select the Fonts Folder.



3. A listing of available fonts will appear. For this screen, select the Lyric.18 font.

NOTE: Be sure the ink color shown in the upper right-hand corner of the screen is black. If it is not, select Ink Color from the Options Menu to change it.

4. Open the TOOLS MENU on the menu bar and select Type.
5. You will see the cursor on the screen. Use the arrow keys, mouse, or joystick to position the cursor where you want to begin typing. Click your pointing device or press the Open Apple key to begin typing. If you need to reposition the cursor, press Esc and use the arrow keys or your pointing device to move it. Once you have started typing, you may only use the Space Bar and the Return and Delete keys to move the cursor. For this tutorial, place the cursor at roughly the same point as shown on the Sample Screen. At the blinking cursor, type: **WHALE WATCH** by (Your Name).

NOTE: If you want to change fonts while you are typing, press Esc. Then press Ctrl-F (the Control and F keys at the same time) to see the Type Font menu.

6. Press Esc twice to return to the TOOLS MENU.


For further instructions on adding text to a Graphic screen see page 84 of the Reference Guide. For more information on graphic fonts and the OPTIONS MENU see page 97 of the Reference Guide.

Add Clip Art


You can decorate screens and enhance graphic backgrounds with clip art. Or use on-screen clip art icons to designate buttons. Make sure that *HyperScreen* Disk B, Side 1, is in a disk drive.

Follow these instructions:


1. Select Clip Art from the TOOLS MENU. When the Disk Menu box appears, select the Clip Art folder. (Press Tab if you need to switch drives.)



2. Use the arrow keys, joystick, or mouse to scroll through the list of clip art files and select the Button.Icons file. Then choose the Arrows file.



3. Scroll through the clip art and select Outline.Hor.Lg.




4. Use the arrow keys or pointing device to position the arrow at the lower right-hand corner of your screen. Press the Apple key or click to stamp it in place.
5. Press Esc to return to the TOOLS MENU.

For more information on using clip art, see page 86 of the Reference Guide.

Add an Opening Transition

HyperScreen's opening transitions are visual effects that occur when a screen opens. You can use opening transitions to add drama and visual excitement to your creations. There are 15 different opening transitions from which to choose. To use an opening transition, follow these instructions:

1. Select Opening Transition from the TOOLS MENU.
2. The Opening Transition Menu box will appear, listing all the transitions. Scroll through the list to see the choices. Select Vertical Blind.



3. The Vertical Blind opening transition will take place on your screen. When it is finished, the TOOLS MENU will reappear, and there will be a check next to the Opening Transition option on the menu. This check indicates that you have chosen an opening transition for this screen.

For more information on the Opening Transitions function, see page 76 of the Reference Guide.


Step Three: Set the Buttons

Button 1: A Link to Screen Button


The Link to Screen button is *HyperScreen's* basic linking unit. It allows you to link a screen to any other screen within the stack you are working on.

You will use the Link to Screen button to link "Whale Watch's" Home Screen to the second screen: the Intro screen.

1. Open the EDIT MENU on the menu bar.
2. Select Set Buttons from the EDIT MENU.



3. You will see the arrow cursor on your screen. To draw Button 1, hold down the Apple key while pressing a vertical arrow key, and then a horizontal arrow key, or hold down the Action button on your pointing device and drag the joystick or mouse. Position Button 1 in the lower right-hand corner of the screen around the arrow.



4. When you have finished drawing Button 1, its solid outline will become a broken line. If you want to move or alter the button, or if you have made a mistake, place the cursor inside the button and press the Apple key or click. The button will become solid again. To resize the button, position the cursor on the small box in the lower right-hand corner of the button and use the arrow keys or pointing device. To move the button, place the cursor inside the button and use the Apple and arrow keys or the pointing device. Or, delete it by clicking on it and pressing the Delete key.


For more information on setting buttons, see page 53 of the Reference Guide.

Set Button Information

Next you must indicate what type of button you have drawn, and fill in the button information necessary for it to perform its actions.


1. Press Esc to return to the EDIT MENU. Select Set Button Info.

2. Position the cursor inside Button 1 and press the Apple key or click the Action button. The Button 1 Info box will appear.




NOTE: While you are in Set Buttons, you can set button information without returning to the EDIT MENU. Position the cursor inside the button and press the Apple key, or click on your button to make it solid. Then press Ctrl-I or Tab. The Button Info box will appear.


3. Press Return or click on <None> beside the "Type:" prompt to view the button type choices. Select the Link to Screen button from this list.




4. The Button 1 Info box will reappear. Use the arrow keys, joystick, or mouse to move down to the small box marked with an X next to the word "Clickable." The X in the box indicates that Button 1 is set to perform its action when clicked. If you want a button to be non-clickable and unavailable to the user, remove the X by pressing Return or clicking on it. For this tutorial screen, Button 1 will be clickable, so leave the X marked in this box.



5. Move to the next small box next to the phrase, "Do On Opening." If you wanted Button 1 to perform its link to another screen when the Home Screen opened, you would press Return or click to mark an X. For this tutorial screen, leave the Do On Opening box blank.
6. Move down to the "Screen:" prompt and press Return or click on <None> beside it. The Link to Screen Menu box will appear with a list of possible screens to which Button 1 may link the title screen. Select A New Screen.



- Next, you will name the new screen. At the blinking cursor, type **INTRO** to add the new screen to the list of screens on the Open Screen menu. When you select the Intro screen from the Open Screen menu later, an empty screen icon will appear next to it. This icon indicates that the screen exists, but has not been worked on yet.



Press Return or click OK. You will return to the Button 1 Info box and see your completed information.


Press Esc twice to accept the completed button information and to return to the EDIT MENU.

For further instructions on setting button information, see page 54 of the Reference Guide.

Step Four: Preview and Save Your Screen

HyperScreen's preview feature is a great editing tool. When you select Preview Screen, you can quickly check your screen and its buttons, graphics, and transitions at any point in the design process without having to save your work first. On-screen buttons will activate, and Link to Screen and Link to Stack buttons will display a box describing the link. Make any changes after previewing your screen and before saving it. Once you are satisfied with your screen, don't forget to save it!

- Open the FILE MENU and select Preview Screen. After the opening transition occurs, a hand icon will appear. You will see all the text and graphics you have added to your screen so far. Move the hand icon and press the Apple key or click on the right arrow icon, Button 1. A box will appear describing what type of button it is, and the name of the screen to which it is linked. Check the screen link for the Link to Screen button you have just set.




- Press Return or click OK to continue. Then press Esc to return to the FILE MENU.
- If you see graphics, text, button positioning or button information you want to change, do so now, before saving the screen.

For more information on Preview Screen, see page 47 of the Reference Guide.

Save Your Screen

Save your Home Screen on your Stack disk. Follow these steps:

- Select Save Screen from the FILE MENU. The Stack Menu box will appear, and under the prompt, "Save WHALE.WATCH Screen:" you will see a blinking cursor next to "Home Screen."




NOTE: Be sure that your Stack disk is in a drive. Your Stack disk is the original disk on which you began your HyperScreen creation.

2. Press Return or click OK to save this screen as the Home Screen.
3. A "Saving the screen..." message will appear on the screen. When the screen is saved, you will return to the opened FILE MENU.

For more information on the Save Screen function, see page 45 of the Reference Guide.

Step Five: Browse Through Your Creation

If you'd like to see how the Home Screen of the "Whale Watch" stack functions, select Browse from the FILE MENU. However, you will not be able to see your screen link yet. You may want to postpone browsing until you have created your second screen and you can see the screen link in action.



Move and click the hand icon to see the screen's button in action. Your screen will show the existence of a link to the new blank screen called Intro by displaying the message, "The next screen does not exist."


Press Return or click OK, then press Esc to return to the menu bar.

For more information on Browse, see page 38 of the Reference Guide.

The Intro Screen


Now you'll create the Intro screen to introduce users to whale terminology.

Your finished screen will look like this:



Step One: Create Your Screen

Select Open Screen from the FILE MENU. At the Open Screen menu, select Intro.




Make this screen a graphic screen.

Step Two: Design Your Screen

1. With *HyperScreen* Disk B, Side 1, in a disk drive, select Graphic Background from the TOOLS MENU. When the Disk Menu box appears, select the Ocean background. The message, "OK to replace the current screen with the new background?" will appear. Press Return or click OK to add the Ocean background to the Intro screen. Press Esc twice to return to the TOOLS MENU.

2. Select Border from the TOOLS MENU. The Classic border will appear around your screen, and you will see the Border option box in the center of your screen.



You now have three options: Remove Border, Change Border, and Redraw Border. For more information on Borders, see page 75 of the Reference Guide.

Press Esc to accept the classic border. The TOOLS MENU will reappear, and there will be a check next to the Border option on the menu. This check indicates that you have chosen a border for this screen.

3. To add the whales, select Clip Art from the TOOLS MENU. When the Clip Art menu appears, press the backslash key (\) to close the previous Clip Art file and select the Animals file. Select the Whale clip art. Using your pointing device or the arrow keys, position the whale in the position indicated on the sample screen and stamp it in place by clicking or pressing the Apple Key.
4. To add the right arrow, press Esc to return to the TOOLS MENU. Then select Clip Art again and close the Animals file. Select the Button.Icons file. Then choose the Arrows file and select Outline.Hor.Lg. Position it in the lower right-hand corner of the screen and stamp it. Press Esc to exit and to return the TOOLS MENU.
5. To add text, select Type from the TOOLS MENU. You will see the type cursor on the screen. Press Ctrl-F (the Control and F keys together) to see the Type Font Menu. Choose the System 8 font and type the text that is shown at the top of the Intro screen. Press Esc twice to return to the TOOLS MENU.

NOTE: You may also see the Type Font menu by selecting Graphic Fonts from the OPTIONS MENU.

6. Select Opening Transition from the TOOLS MENU and when the Opening Transition menu appears, choose the Fade to Black transition to enhance this screen. After you have made your selection, the TOOLS MENU will reappear.


Step Three: Set the Buttons

Button 1: A Sound button

Button 2: A Link to Screen button

Now you will create a Sound button that will perform a sound effect of the ocean when the screen opens. You can set as many sound buttons on a screen as you like, but only one sound per screen may be used. So, if you set more than one sound button on a screen, each button will play the same sound. The Link to Screen button will take you to the next screen.

1. Open the EDIT MENU on the menu bar. Select Set Buttons from this menu and draw Button 1 in the position shown below.



Click on the broken-line outline of Button 1 to make it solid. Then press Ctrl-I or Tab to see the Button 1 Info box.

2. Click on <None> beside the "Type:" prompt, and select the Sound/FX button from the list of button-types. When the Button 1 Info box reappears, press Return or click on the box to make Button 1 non-clickable. Move down to the Do On Opening box and press Return or click on it to set the button to perform when the screen opens.
3. Move the box outline down to where <None> appears next to "Effect:" Press Return or click here. Be sure *HyperScreen* Disk B, Side 2 is in a drive and select the Sound folder. The sound choices will appear. Select the Sound Effects folder, and choose Rushing.Water.
4. The sound will play and the sound box will appear. The Sound box presents three choices: Remove Sound/FX, Change Sound/FX, and Play Sound FX. Press Esc twice to accept this sound effect and your completed Button 1 information. Then, press Esc until you return to the EDIT MENU.

For more information on Sound/FX buttons, see page 66 of the Reference Guide.

As you did on page 114, set a Link to Screen button (Button 2) in the position indicated on the sample screen. Make it a clickable button. Link the Intro screen to A New Screen called **MAP**.

Step Four: Preview and Save Your Screen

Open the FILE MENU and select Preview Screen to check your screen for any changes you'd like to make. After you preview it, make any changes and correct any mistakes on your screen. When you are satisfied with your work, select Save Screen from the FILE MENU and save your screen.


Step Five: Browse Through Your Creation

If you'd like to see your first two screens in action, select Browse.

The Map Screen

Now you will create the Map screen which will display a few whale facts.

Your finished screen will look like this:



Step One: Create Your Screen

Select Open Screen from the FILE MENU and when the Disk Menu box appears, choose Map. Make this a Graphic screen.

Step Two: Design Your Screen

1. With *HyperScreen* Disk B in a disk drive, open the TOOLS MENU and select Graphic Background. Then select the World.Map graphic. Press Esc twice to return to the TOOLS MENU.
2. Select Clip Art from the TOOLS MENU. As you did in the previous two screens, select the Outline.Hor.Lg from the Arrows file, position it in the lower right-hand corner and stamp it.
3. Press Esc and when the TOOLS MENU reappears, choose Clip Art again. Close the Arrows file and Button.Icons file and select Round.Button.1 from the Button.Shapes file this time. You will stamp it on the screen in two places. Use the sample screen as a guide.
4. Press Esc to return to the TOOLS MENU.

Step Three: Set the Buttons


Buttons 1 & 2: Pop-up Text buttons

Button 3: A Multi-button

Button 4: A Link to Screen button

Buttons 1 and 2:

1. Open the EDIT MENU and select Set Button. Draw Button 1 over the first Round Button in the position indicated on the sample screen below:



Press Esc to return to the EDIT MENU and select Set Button Info. Click on Button 1 to view the Button 1 Info box.

NOTE: You can also press the Apple or Esc keys, or click on your button and then press Ctrl-I or Tab to view the Button 1 Info box without returning to the EDIT MENU.

2. Press Return or click at <None> which appears after the "Type:" prompt in the Button 1 Info box to view the Button Types menu. Scroll through this list and select Pop-up Text button.

When the Button 1 Info box reappears, keep the button "clickable."

3. Press Return or click on <None> which appears after the "Text:" prompt. The Pop-up Text Message box will appear on the screen. Type **Baleen whales have no teeth. They strain food through bristly plates called baleen, and swallow.**
4. Check your message for typing errors. If you see any mistakes, use the Back Space key to delete individual letters or press Ctrl-Z to undo all of the text you have just typed. When you have made your corrections, press Esc to accept the message you have typed. Press Esc twice to accept your button information and to return to the EDIT MENU.


- Repeat the same steps for Button 2, and position it over the second Round Button in the place indicated on the sample screen. Set the same Pop-up Text button information, but type in the message box: **Toothed whales use their teeth to catch prey and to tear food into pieces. They are hunters.** Press Esc to return to the Menu Bar.

For more information on Pop-up Text buttons, see page 64 of the Reference Guide.


Button 3

On this screen, the Multi-button will not be clickable and will automatically activate Buttons 1 and 2. Even though the Multi-button will sequence your buttons automatically, you will set your pop-up text buttons as "clickable" on this screen. As such, after they perform in sequence on opening, the user will be able to click on them and read their messages again. Now set the Multi-button to sequence the buttons on your screen.

- Select Set Button from the EDIT MENU and draw Button 3 anywhere on the screen. Click on the button, and then press Ctrl-I or Tab to view the Button 3 Info box. At the "Type:" prompt in the Button 3 Info box, press Return or click to view the Button Type choices. Select Multi-button.
- When you return to the Button 3 Info box, make the button non-clickable. Press Return or click on the Do On Opening box so that the Button 1 and Button 2 Pop-up Text will appear automatically.




- At the Buttons prompt press Return or click at <None> to see the Multi-button List box.



Type the numbers of your buttons to indicate the order in which you want them to be activated. For this tutorial, type 1, 2. Then press Esc.

- The completed Button 3 Info box will appear on the screen. Press Esc to accept the information on it. Press Esc until you return to the EDIT MENU.



For more information on the Multi-button, see page 62 of the Reference Guide.

Button 4

As you did in the previous two screens, create a Link to Screen button and position it over the arrow. In the Button Information box, keep this button clickable and link it to a new screen named Q/A.

Step Four: Preview and Save Your Screen

Preview your screen and make any changes you wish to make now. When you are finished editing, save your screen.


Step Five: Browse Through Your HyperScreen Creation

If you wish, you can select Browse from the FILE MENU and browse through the screens you have created so far.

The Q/A Screen

Now you will create the Q/A screen. On this screen you will see a question based on information provided in the two previous screens.

Your finished screen will look like this:



Step One: Create Your Screen

Select Open Screen from the EDIT MENU. When the Open Screen menu appears, choose the Q/A screen and make it a Graphic screen.


Step Two: Design Your Screen

1. Make sure that *HyperScreen* Disk B, Side 1, is in a disk drive and select Graphic Background from the TOOLS MENU. When the Disk Menu box appears, select the Backgrounds folder. Then select the Notecard graphic from the list of backgrounds. Press Esc twice to return to the TOOLS MENU.
2. Select Type from the TOOLS MENU. Press Ctrl-F to select a font. If you want to type the title in a different font, use Plaza.12. For the rest of your text you will use the System 8 font. When the cursor appears, position it and click to begin typing. Then type the text shown on the sample screen. Press Esc twice to return to the TOOLS MENU.
3. Select Clip Art from the TOOLS MENU. Then select the Help.Lg icon. from the Organization file in Button.Icons. Position the question mark underneath the instructions.
4. Select Opening Transition from the TOOLS MENU. When the Opening Transition menu appears, select Checker Spiral. The Checker Spiral opening will run and you will see how it looks.

Step Three: Set the Buttons


Button 1: A Text Entry Button

1. At the EDIT MENU, select Set Buttons. Draw Button 1, the Text Entry button, around the text entry button icon, in the position indicated on the sample screen below.




When you are finished, click inside the button, and then press Ctrl-I or Tab to set the Button 1 information.

2. When the Button 1 Info box appears, press Return or click at the Button Type prompt. Select Text Entry from the list of button types. You will then see the Text Entry Button 1 Info box. Keep this button clickable.




3. Move down to the Match prompt. Here you will enter the text the user must type for a correct or Yes match. At the Match prompt, press Return or click to enter the match in the Text Match box. Type `|BALEEN WHALE_OR_BALEEN WHALES_OR_BALEEN|` as the match here and press Esc.




You will return to the Button 1 Info box. Move down to the If Yes prompt. The If Yes prompt asks you for the name of the screen you wish to link to if the text in the Match prompt is correctly typed on the screen.

4. Press Return or click at the If Yes prompt to see the Yes Match Screen menu. Select A New Screen and name it **STATES**. Press Return or click OK to return to the Button 1 Info box.
5. Move to the If No prompt. Here you are asked for the name of the screen to which the user will link if the text at the Match prompt is not correctly typed on the screen. When you click at this prompt, you will see the No Match Screen menu.



Select A New Screen and name it **TYPES**. (You will add information about the two different types of whales on this screen.) Press Return or click OK to return to the Button 1 Info box.

7. The final step of setting the button information for the Text Entry button is setting the position of the text entry blank. Move to the bottom of the Button 1 Info box. Click at the Set Entry Blank prompt. An adjustable rectangle will appear on your screen. You can move and resize it the same way you move and resize a button. You can make it as wide as your screen, but it cannot be taller than about half an inch, or the height of one System 8 font character.



Position the entry blank under your Text Entry button, as shown in the sample screen above. When it is in position, press Esc to return to the Button 1 Info box. Press Esc to accept what you have entered in the Button 1 Info box. Then press Esc again until you return to the EDIT MENU.

Step Four: Preview and Save Your Screen

Check your screen for mistakes and incorrect button information. When everything is correct, save your screen.

Step Five: Browse Through Your HyperScreen Creation


Use the Browse function to see your screens in action.

For more information on Text Entry buttons, see page 68 of the Reference Guide.

The Types Screen

Now you will create the Types screen which is the No Match screen link. If the wrong answer is entered in response to the text entry question, the user will be sent to this screen, which provides further information on baleen and toothed whales. Once the user reads this information, she is sent back to the previous Q/A screen via a Link to Screen button. The user has another chance to answer the question correctly, and to continue through the Whale Watch stack.

Your finished screen will look like this:



Step One: Create Your Screen

Select Open Screen from the FILE MENU. Select the Types screen from the Open Screen menu and make it a Text screen.

Step Two: Design Your Screen

1. Make sure that *HyperScreen* Disk B, Side 2 is in a disk drive and select Border from the TOOLS MENU. The Classic border will appear on your screen. You will then see three options: Remove Border, Change Border, and Redraw Border. Select Change Border. When the Disk Menu box appears, select the Borders folder. Then choose Shadow. Press Esc to return to the TOOLS MENU.
2. Select Text Editor from the TOOLS MENU. Type the text shown on the sample screen above, including the text at the lower right-hand corner.
Press Esc to return to the TOOLS MENU.
3. Select Opening Transition from the TOOLS MENU. Choose the Checker Wipe opening transition. After the transition takes place on screen, the TOOLS MENU will reappear.

Step Three: Set the Buttons

Button 1: A Link to Screen button

1. At the EDIT MENU, select Set Buttons. Draw Button 1 in the lower right-hand corner of the screen, around "Go Back."
2. When you are finished drawing, click inside the button to make the button outline solid, and press Ctrl-I or Tab to set the button information.
3. When the Button 1 Info box appears, press Return or click at the "Button Type" prompt. Select Link to Screen from the list of button types. Keep this button clickable.

4. At the "Screen:" prompt, press Return to view the Link to Screen choices. Select Previous Screen. Press Esc to accept the button information. By linking the Types screen to the previous screen, the user is given a second chance to answer the question correctly. Press Esc until you return to the EDIT MENU.

Step Four: Preview and Save Your Screen


Check your screen for any mistakes, misspellings, or incorrect button information. When you are satisfied with your work, save your screen.

Step Five: Browse Through Your *HyperScreen* Creation

Use the Browse function to see your screen or screens in action.

The States Screen

Now you will create the States screen and add eight buttons. This correct match screen will display whale trivia. The Link to Stack button at the bottom of the screen will link to a stack in which you may enter summaries of books, and magazine and newspaper articles about whales.



Go to the FILE MENU and select New Stack. When you are asked to name the new stack, at the blinking text cursor, type **REFERENCES**. Press Return or click OK. When the Text or Graphic Screen Option box appears over the Home Screen of the References stack, make the first screen a text screen. You can return to this screen later and change this selection. Now select Open Stack from the FILE MENU and reopen the "Whale Watch" stack.

Step One: Create Your Screen

Select Open Screen from the FILE MENU. Then select States from the list of screens. Make this screen a Graphic screen.

Step Two: Design Your Screen

1. Select Graphic Background from the TOOLS MENU. Choose the US.Map graphic. Press Esc twice to return to the TOOLS MENU.
2. With *HyperScreen* Disk B, Side 1 in a disk drive, select Clip Art from the TOOLS MENU. When the Disk Menu box appears on the screen, select the Clip Art folder and then choose the Button.Shapes file.

3. Select the Round.Button.1 icon and stamp it in the four locations indicated on the sample screen. Press Esc to return to the TOOLS MENU and select Clip Art once again.
4. Close the Button.Shapes file and select the Button.Icons file. Then select Information. Choose the small book icon. Press Ctrl-B to add a white border around it and stamp it on the screen in the lower right-hand corner.
5. Select Opening Transition from the TOOLS MENU. Choose Flicker.

Step Three: Set the Buttons

Buttons 1-6: Pop-up Text buttons

Button 7: A Multi-button

Button 8: A Link to Stack button

Button 1

1. Select Set Buttons from the EDIT MENU and draw Button 1 over the button icon you have stamped on Hawaii's coast.
2. Click inside Button 1 to make its outline solid and press Ctrl-I or Tab to view the Button 1 Info box. Click at the Button Type prompt, and make this button a Pop-up Text button. When the Button 1 Info box reappears, keep this button clickable.
3. Scroll down to the "Text: " prompt and type the following: **Humpback whale songs change annually. Only the males sing. Humpbacks mate in the waters off Hawaii.**
4. When you have completed typing your message, press Esc. Press Esc twice more to accept your button info and to return to the EDIT MENU.

Button 2

Position your second Pop-up Text button over the button icon you have placed near the coast of Washington state. Repeat the steps above, except type the following: **Orcas have no natural enemies. Hunting in packs, they can kill and eat whales three times their size.**

Button 3

Position your third Pop-up Text button over the button icon you have placed off the Massachusetts coast. Repeat the steps above, but type: **Sperm whales are deep water divers. They create an intense sound in their skulls to stun their prey.**

Button 4

Position your fourth Pop-up Text button over the button icon you have placed off the Southern California coast. Repeat the steps above, but type: **Dolphins use a form of sonar called echolocation to find food and to navigate.**

Button 5

Position your fifth Pop-up Text button anywhere on the screen, but not over one of the buttons you have already created. Repeat the steps above for a Pop-up Text button, but make it non-clickable—remove the "X" in the Clickable box. When the message box appears, type: **Click on the buttons to see where some whale species are sighted and to learn more about them.**

Button 6


Position your sixth Pop-up Text button as you positioned Button 5 (anywhere on the screen), and make it non-clickable, as you did Button 5. When the message box appears, type: **Click on the book icon to read whale book and article summaries.**

Button 7

As you did in the Map screen, draw a button anywhere on the screen, make it a Multi-button, non-clickable, and choose "Do On Opening" from the Button 7 Info box. Click on the "Buttons:" prompt and when the Multi-button List box appears, type: **5, 6.** Now the Button 5 and 6 message boxes will appear automatically when the States screen opens.

Button 8

1. Select Set Button from the EDIT MENU and draw Button 8 in the lower right-hand corner, over the small book icon.
2. Click inside Button 8 and then press Ctrl-I or Tab to view the Button 8 Info box. Click at the Button Type prompt, and make this button a Link to Stack button. When the Button 8 Info box reappears, keep this button clickable.
3. Scroll down the Button 8 Info box and press Return or click at the Stack prompt. The Stack menu will appear.



Select the References stack. When you see the completed Button 8 Info box, press Esc to accept the information you have entered and to return to the EDIT MENU.

Step Four: Preview and Save Your Screen

Check your screen for mistakes and incorrect button information. When everything is correct, save your screen.

Step Five: Browse

Use the Browse function to see how your creation looks and functions.

The Stack End Screen

HyperScreen allows you to create and save screens, then return later and connect them to other screens. You can designate the stack end at any point by using a Link to Screen button to link to Stack End on the Link to Screen menu found in Button Info.

Editing Your *HyperScreen* Creation

Did you see any screens, buttons, or links you would like to change? Editing a *HyperScreen* creation is easy.

At the FILE MENU, select Open Screen and choose the screen you want to edit. Use the EDIT, TOOLS, and OPTIONS MENUS to make your changes. Preview your edited screen and don't forget to save it. Now use Browse to see how the edited screen functions.

Now you're on your way to expanding or finishing this practice *HyperScreen* creation. Take a look at the stack design chart on page 105 and see how far you've come. Use the information provided here as a starting point. Look up information on baleen whales such as the blue and minke, use a text screen, and fill in the facts. Find interesting articles on whales, and summarize them in the References stack.

Here are some other suggestions:

- Using the Whale clip art, set a few Pop-up Text buttons on the whale's body. Fill in the names of the body parts and brief descriptions of how they function. The user will be able to click on the whale's body and see pop-up text descriptions.
- Using the World Map background, set Link to Screen buttons at locations on the map where whales live. Then fill in the linked screens with information on predators that whales encounter in their habitats.
- Use the Whale Watch Q/A with Text Entry buttons throughout the stack to quiz users on whale information.
- Using the Link to Stack button, link the Whale Watch stack to an Issues stack in which whale survival issues such as whaling and pollution are discussed and illustrated. Or investigate differences of opinion among whale and dolphin experts on topics such as dolphin intelligence and why whales strand.

Fill in the stack design chart with your new screens and stacks. With *HyperScreen*, you can design and shape creations in your own intuitive way!

APPENDIX A: THE VIDEO CONTROL BUTTON

Equipment You Will Need

You can use *HyperScreen* with a Pioneer LD-V4200 videodisc player. For an Apple IIe, you will need an Apple II Super Serial Card to connect the player to your computer. For the IIc and IIc Plus, you will use the modem port for connecting. For the IIGS, you can use either the modem port or the Apple II Super Serial Card, as you prefer. To combine *HyperScreen* graphics with video onto one monitor, you will need the Apple II Video Overlay Card. Since the Apple II Video Overlay Card uses an expansion port, Apple IIc and Apple IIc Plus users will be unable to use this card.

Pioneer manufactures the necessary cables to connect the LD-V4200 to an Apple computer. Use cable model CC-04 to connect the videodisc player via the Modem Port. Use cable model CC-03 to connect the videodisc player via the Apple II Super Serial Card.

Setting Up

To properly connect your equipment, read through the section(s) that apply to your machine. For additional clarification you may want to refer to the following manuals, all provided by either Apple or Pioneer, when you purchased their equipment:

- Apple II Super Serial Card User's Manual
- Apple II Video Overlay Card Owner's Guide
- Apple IIGS Owner's Guide
- Setting Up Your Apple IIGS
- Pioneer LD-V4200 Operating Instructions
- Apple IIc/IIc Plus Owner's Guide

Using the Modem Port (Apple IIGS, Apple IIc, and Apple IIc Plus)

Using the built-in modem port in your computer simplifies your setup. Plug in the proper cable from the interface port in the back of your videodisc player to the modem port in the back of your computer.

Apple IIc or IIc Plus With the computer turned off, plug cable CC-04 into your modem port referred to as Port 2.

Apple IIGS With the computer turned off, plug cable CC-04 into your modem port. Go to the IIGS Control Panel and under the Slots menu, ensure that Slot 2 is at its default setting of "Modem Port."

Check that all the selections under the Modem Port menu are at their default settings; in other words, that every selection on the menu is preceded by a check mark. If this is not the case, change the item so that the check mark appears.

For further instructions on using the IIGS control panel, consult the Apple IIGS Owner's Guide or Setting Up Your Apple IIGS provided when you purchased your computer.

Using The Apple II Super Serial Card
(Apple IIGS, IIfx)


The following is an abbreviated set of instructions on how to configure your serial card and insert it in your Apple computer. For more detailed instructions consult your Apple II Super Serial Card User's Manual.

WARNING: Never have your computer turned on when you are inserting or removing a card. This also applies to changing switch settings while a card is in the machine. Please be careful!

- 1. Adjust the switch settings and jumper block on your Super Serial Card.

You'll find the switches in the upper left-hand corner of your card. The following diagram shows you two types of switches in the off and on positions, depending on your card type. Find the type which matches your card. Your card may also use Closed to mean the On position.

Two switches set to ON and OFF




The switch settings are:

Table with switch settings for Switch 1 and Switch 2. Switch 1 settings: 1-1 OFF, 1-2 OFF, 1-3 ON, 1-4 ON, 1-5 ON, 1-6 ON, 1-7 ON. Switch 2 settings: 2-1 ON, 2-2 ON, 2-3 ON, 2-4 ON, 2-5 OFF, 2-6 OFF, 2-7 OFF.

Set the jumper block to Modem.

The diagram below illustrates the settings.



- 2. Place the card in a slot in your computer. Slot 2 is recommended.
3. Connect your Super Serial Card to your videodisc player's interface port with Pioneer Cable model CC-03.

For the IIGS When using the Super Serial Card to connect the IIGS to your videodisc player, to check your setup, go to the Control Panel of your IIGS and choose the Slots menu. The words "Your Card" should appear next to the slot number in which you placed the Super Serial Card.

The Video Overlay Card

Follow the instructions that came with your Apple II Video Overlay Card to install the card into your computer. The Video In jack should be connected to the Video Out jack of your videodisc player. The card's Video Out jack can go into the Video In jack of any recording or monitoring device (VCR, TV, monitor).

For the IIGS When using the Video Overlay card with the IIGS, check the slots menu on the Control Panel. The words "Your Card" should appear next to the slot number in which you have placed the Video Overlay card.

Setting Up the Pioneer LD-V4200

You will need to set the function switches located on the front panel of the LD V4200 videodisc player. Consult the LD-V4200 Operating Instructions for directions on changing switch settings. Follow these guidelines as you set the switches:

- 1. The first three switches do not affect the videodisc/computer setup. You may set them as you wish.
2. Switch 7 must be in the up position (at the setting for 4800 bit/sec).
3. Switches 6 and 8 must be in the up position.
4. Switch 5 is optional. The up (default) position is recommended. In this position, your background screen will appear entirely blue when your player is on, but no disc is playing. This way you can easily note that your player is turned on.

We recommend setting all 8 switches in the up position.

Testing Your Setup

To test your videodisc player and/or video overlay setup follow the steps below.

Testing Your Super Serial/Modem Port Setup

- 1. Turn on your videodisc player. Insert a disc in your player. Then load HyperScreen in your computer. The disk must not be playing.
2. Click on the icon called Disc Explorer on the HyperScreen Home Stack.
3. Read the Home Screen, check your setup, and then click on the button marked Test Player.

NOTE: The Test Player button is configured for port/slot number 2. If you are using another port or slot for your Super Serial Card, use Set Button Info to change the port/slot to the appropriate number.

4. You will see the videodisc player's play light blink a few times. A picture will appear on your monitor (if you are using the Overlay Card you should see it on your computer screen). It will play for a few seconds and then stop.

5. If you see the error message, "Port not usable for video control," your Super Serial Card is not in port/slot 2 (or another slot you specified). Place your card in the correct slot.

If you see the error message, "Player disconnected or not turned on," then your player power is off, the cable is not connected, or is damaged.

The error message "Video Command not correct or player not ready" means that the disc is not in the player or someone has changed the test button commands.

If nothing happens, press Esc. This means the switches or jumper cable on the Super Serial Card are not set properly or the IIGS port is not set to default.

Testing Your Video Overlay Setup

- 1. Turn on your videodisc player. Insert a disc in your player. Then load HyperScreen in your computer.
- 2. Press Play on the videodisc player's front panel.
- 3. From the HyperScreen Home Stack, press Esc. From the Options menu select Video Key Color.
- 4. Select All as your Video Key Color.
- 5. When you see the menu bar, press the Space Bar. In place of your computer image you should see a video image. Press the Space Bar again to bring the menu bar back into view.

If you do not see a video image, your equipment may be connected incorrectly. Check cables and cards for any loose connections or possible damage. If necessary, disconnect cables and cards and start from the beginning. To check connections on the IIGS, see the note on page 139.

THE COMMANDS

HyperScreen recognizes 27 Pioneer commands and has two built-in commands.

NOTE: The Pioneer LD-V4200 recognizes 37 commands, but due to their complexity, 10 of these commands cannot be accessed by HyperScreen.

The table below lists the commands used with HyperScreen. CAV and CLV refer to different videodisc formats. See the Glossary on page 154 for a complete description of the differences.

	Commands	Mnemonic	CAV or CLV?
1	Audio Control	number AD	Both
2	Chapter	CH	Both
3	Clear	CL	Both
4	Clear Screen	CS	Both
5	Display Control	number DS	Both
6	Door Open	OP	Both
7	Frame	FR	CAV
8	Key Color	KC number	Both
9	Key Lock	number KL	Both
10	Multi-speed Forward	(number) MF	CAV
11	Multi-speed Reverse	(number) MR	CAV
12	Pause	PA	Both
13	Play	(number) PL	Both
14	Print	number PR	Both
15	Register A	number RA	Both
16	Register B	number RB	Both
17	Reject	RJ	Both
18	Scan Forward	NF	Both
19	Scan Reverse	NR	Both
20	Search	number SE	Both
21	Speed	number SP	CAV
22	Start	SA	Both
23	Step Forward	SF	CAV
24	Step Reverse	SR	CAV
25	Still	ST	CAV
26	Stop Marker	number SM	Both
27	Time	TM	CLV
28	Video Control	number VD	Both
29	Wait	WA number	Both

How to Use The Commands

This section is divided into two sub-sections, Basic and Advanced.

If you have any problems understanding the sections, you might try to "dissect" the Disc Explorer stack. Take apart the buttons used in the stack and see if you can gain a better understanding of them by comparing how a button is structured to what it does when pressed. Experiment as much as you can. If you receive the error message "Video command not correct or player not ready," check the text in your command box against the command list for misspelled commands or incorrect numbers. You may wish to plan ahead and have your command sequences already written out on paper.

Basic Commands

NOTE: The letters in parentheses are the Mnemonic codes you will type in for these commands.

Door Open (OP)

Door Open serves one purpose: it opens the tray door of the LD-V4200. If you use it while the player is playing a videodisc, the player will stop before ejecting the disc.

Examples:

1. OP - Tray opens.
2. OP - Stop rotation, open tray. (If disc hasn't been stopped yet.)

Pause (PA)

Pause can be used on either CAV or CLV discs. It freezes the disc and displays the blue screen. A CLV disc should not be left on Pause for more than 15 minutes.

Example:

PA - Pause disc and display blue screen.

Play (PL)

Play is the most basic command. It plays a disc. If the disc has not been started, it plays the disc from the beginning. If the disc is already playing, the command has no effect. If the disc is either paused or still, it will begin playing again. Optionally, you can set a location (frame or time) where the player will stop playing.

This command is usually used singly, but it may also be used in conjunction with the Search command (see below). Search moves to the appropriate frame/time/chapter and Play starts playing the disc from that point.

Examples:

1. PL - Play the disk.
2. FR 24050PL - Play from beginning and pause when frame 24050 is reached.

Reject (RJ)

This command stops the player. If the player has already stopped, the command will eject the tray (similar to Door Open above).

Examples:

1. RJ - Stop disc rotation.
2. RJ - Open disc tray. (If already stopped)

Scan Forward/Reverse (NF, NR)

Similar to Step, this command, instead of taking single frame jumps, moves the disc forward or reverses in large jumps. The disc must be playing or paused for this command to work. It works with both disc types. With CAV discs, a jump averages 500 frames. For CLV discs, a jump is about 20 seconds. Use this command to quickly scan a disc for a particular sequence. If you are looking for a particular frame, remember jumps are large and may skip over the specific frame.

Examples:

1. NR - Jump back about 500 frames.
2. NF NF NF - Jump ahead about 1500 frames.

Search (SE)

This command will search for a specific location of an image on the videodisc. Type in the location (frame, time, or chapter) before the command code. The player will jump to that location and then still or pause the image. When used with Play, after the located image has been found, the disc will continue playing from that point.

Examples:

1. FR 4500SE - Search for frame 4500 and then Still (CAV).
2. CH 5SE - Search for chapter 5 and then Pause (CLV).

Start (SA)

Start will start the player and still or pause at the very first screen on the disc. A CAV disc will still at frame 00001; a CLV disc will pause at time 0.00:01. Using this command while a disc is already playing will set the player back to the First Screen, then pause. This command is useful for quickly jumping back to the beginning of a disc, and for ensuring a disc is ready when beginning a series of screens with video control buttons.

Examples:

1. SA - Start disc and pause at first screen.
2. SA - Reset disc to first screen and then pause (if disc is already playing).

Step Forward/Reverse (SF, SR)

When a disc is playing, these commands step through the disc, forward or backward frame by frame. This works only with CAV discs. Use this command if you want to see a particular sequence on the disc, one frame at a time.

Examples:

1. SF - Move forward one frame.
2. SR SR SR - Move back three frames, one frame at a time.

Still (ST)

This command freezes a CAV disc and displays the frame on the screen. When creating interactive lessons, the command can be used to display a single frame on the disc.

Example:

ST - Pause and display picture.

Wait (WA)

This *HyperScreen* command will momentarily pause the program between commands. In conjunction with the Still command, you can use this command to create a "slideshow" of single frames with pauses in between. The number you give it is the amount of seconds (99 maximum) *HyperScreen* will wait before executing the next command. Be aware that the number is entered to the right of the command, not the left. The number must be followed by a space.

Examples:

- 1. ST WA10 PL - Still the image, wait 10 seconds, and then resume playing.
- 2. PL WA30 OP - Play the disc, wait 30 seconds, open the tray door.

Sample Basic Command Boxes

Below are several sample command boxes using basic commands that you could use when setting the button information for a video control button. Beside each is a description of the actions it will produce on your screen. Each of these samples assumes that Key Color on the *OPTIONS* MENU of your *HyperScreen* program is set to None.

Test Set Up

Video Command
SA PL PL PL WA10 RJ
Press Esc to accept.

This will:
Start player, play disc, (using several commands to advance past any initial stop codes on the disc), wait 10 seconds, stop player.

Show Series of Stills

Video Command
SA FR 1000SE WA3 4000SE WA3 300SE WA3 SF WA3
Press Esc to accept.

This will:
Start player, display images at frames 1000, 4000, 300 and 301 for 3 seconds each, leave player running with last image on screen.

Show Video Clip

Video Command
FR 5000SE 6000PL WA5 5000SE
Press Esc to accept.

This will:
Assuming player is running, go to frame 5000, play to frame 6000, wait 5 seconds, return to the original image, and leave it on the screen.

Advanced Commands

Audio Control (AD)

Videodiscs have two audio tracks, often used together to give stereo sound. Unless you connect your videodisc player to a stereo system or are using a stereo monitor, you will not get the stereo effect. Some videodiscs, instead of using two tracks for stereo, use one track for one type of audio and the other track for a different type of audio. For instance, a videodisc might contain English on one track and Spanish on the other track. Or it might contain commentary on one track and music on the other track. Audio Control allows you to control which track you will hear by setting the audio channels within the videodisc player.

To control the channels, place a number before the command code. The chart below shows you the numbers and their effects.

Number	Function Name	Channel One	Channel Two	What You Will Hear
0	Off	Off	Off	No Sound
1	Track 1	On	Off	Track 1 only
2	Track 2	Off	On	Track 2 only
3	Stereo	On	On	Track 1 and Track 2 on their respective channels

Examples:

- 1. 1AD - The sound coming out of both speakers is from the disc's channel one.
- 2. 2AD - The sound coming out of both speakers is from the disc's channel two.
- 3. 3AD - The sound coming out of both speakers is from the disc's channel one and channel two, respectively (stereo).

Chapter (CH)

(See Frame/Time/Chapter, page 147.)

Clear (CL)

With the Clear command, all values stored under commands which ask for a location are cleared. This means that commands like Search, Play (if auto-stop is activated), and Stop Marker "release" themselves. If Clear is executed while Searching a disc, the player empties the Search Number and Stills or Pauses immediately. If cleared during an auto-stop or Stop Marker operation, their respective numbers are cleared and normal play resumes.

Examples:

- 1. FR 4000PL - Play the disc from the beginning until frame 4000 is reached and then pause.
- CL - Ignore the previous command and play the disc normally.

- 2. CH 2SE - Search the disc for chapter 2 and then Still (CAV) or Pause (CLV) the disc.

CL - Release the Search command and then Still (CAV) or Pause (CLV) the disc immediately.

Clear Screen (CS)

This command clears the user's portion of the display area. (The display overlays the entire videoscreen area. See the Glossary for a complete description.) For instance, you may have placed text over the screen with the Print command and now wish to erase it. Since Clear Screen clears the entire user's portion, if you wish to erase only one line of your text, use the Print command to print blank spaces over that line.

Example:

CS 3P - Clear the screen and move cursor to the start of a new line.

Display Control (DS)

This command determines whether the display area is turned on or off. (See the Glossary for a complete description of the display area.) The display overlays the entire videoscreen area. The top of the display area contains the set of characters and numbers indicating what frame, time, and chapter you are currently viewing. The bottom of the display area is the user's portion containing any text you enter with the Print command. Use the Display Control command in conjunction with Print and/or Register A commands (See page 148) for captioning or showing users what sections they are watching.

Setting the Display Control to 1 turns on the display. The default value is set to 0 (off).

Example:

1DS - Show the display.

Frame/Time/Chapter (FR, TM, CH)

These three commands will set a location for other commands to operate. They are placed before commands like Play and Search. Normally, the player will expect Frame numbers when you supply a number to commands like Play, Search, and Stop Marker. If you use Time or Chapter, the same commands will consequently expect either Time or Chapter numbers. The maximum frame number is 65535, maximum time code is 75959, maximum chapter number is 79. If you exceed these numbers on your commands, you will get an error message.

Examples:

- 1. FR 1000SE - Frame number 1000 is searched for.
- 2. FR 34020PL - Play the disc until Frame number 34020 is reached.
- 3. TM 2013PL - Disc plays until Time number 0.20:13 is reached.
- 4. TM 1202SE - Search the disc for Time number 0.12:02.
- 5. CH 3SE PL - Disc skips to Chapter 3 and then plays.
- 6. 30SP CH2MF - Disc is played forward at half the speed until Chapter 2 is reached.

Key Color (KC)

With this *HyperScreen* command you can control the video key color from within the Video Control button. To use this, you need a Video Overlay Card. When you select a video key color, the areas of your computer screen in that color become transparent and the video image shows through. The command will accept a number between 0 and 7. The number sets the key color in the order shown on the video key color menu on the OPTIONS MENU: 0 = none, 1 = Black, 2 = Violet, 3 = Blue, 4 = Green, 5 = Orange, 6 = White, 7 = All. Enter the number to the right of the command, not the left. The number must be followed by a space. For a more complete description, see Video Key Color in the OPTIONS MENU section of the User's Guide.

Example:

KC4 - Set the color Green as the key color. Green becomes transparent, and your video image will show through.

Key Lock (KL)

This command locks your player's front control panel (other than the power button) and prevents someone from overriding a sequence of commands you executed. All buttons, except for the power button, are ignored. The number 1 before the command sets the Key Lock on, and 0 turns it off. The Key Lock lamp on the front panel of the videodisc player will turn on when set to 1.

Example:

1KL - Lock the front panel. All the keys are disabled, except for the power switch.

Multi-Speed Forward/Reverse (MF, MR)

This command is used in conjunction with the Speed command. It will play the disc faster or slower than normal. You can set a location for it to play up to; the image will then Still at that point. It can play a disc from one-sixth as slow to four times as fast as normal speed.

Examples:

- 1. MF - Play the disc forward at the speed given within the Speed register.
- 2. FR 340MR - Play the disc backward until frame 340 is reached, at the speed given within the Speed register.

Print (PR)

The user's portion of the display area is made up of 8 or 11 lines of text , depending on your machine. (See the Glossary for a more detailed description.) You can place text over the videoscreen on any line with this command. This command takes up two lines. Preface the command with the number of the line on which you want to place text ; then press Return and type in a line of text up to 20 characters. Follow this sequence for each line of text you want to display. This command only works when the Register A command has been entered, making the user's area visible (see below).

Example:

4PR - Set up user's display to accept text for the fourth line.
HELLO WORLD! - Hello World! is printed on the fourth line, on the screen.

Register A (RA)

This register sets what portion of the Display Area is visible on the screen. (See the Glossary for a complete description of the display area.) The uppermost portion of the display area contains the frame/time and chapter numbers adjacent to each other. Below is the user's portion on which you can place text using the Print command. You can use this command to make any single area visible (user, frame/time, or chapter), any combination of areas visible, or all areas visible.

The table below shows the number to place before the command code for all eight possible combinations of the three areas.

Number	User's Area	Chapter	Frame/Time
0	-	-	-
1	-	-	On
2	-	On	-
3	-	On	On
4	On	-	-
5	On	-	On
6	On	On	-
7	On	On	On

Examples:

- 1. 1DS - Display is turned on.
- 2RA - only Chapter area is visible.

Register B (RB)

This register controls what the player will "censor" (squench) from the user. Normally, video and audio are shut off whenever the machine performs a Scan or a Search. Overriding it will allow the user to see and hear everything that is happening, even compressed audio and video when the player is playing four times faster than normal. The default is 0. The following table shows you all the possible combinations created by placing a number before the command code.

Number	Video	Audio
0	Normal	Normal
64	Normal	Off
128	Off	Normal
192	Off	Off

Examples:

1. 128RB - Video squelch is turned off.
2. 192RB - Video/audio squelch is turned off.
3. 0RB - Back to normal.

Speed (SP)

This command is what sets the speed register which controls the playing speed when Multi-Speed is executed. This can be set at any time, but most often will be set before executing Multi-Speed. There are 255 possible speeds.

Sixty is normal play and the default value. The relationship between the Speed Number and actual speed play is as follows.

$$\text{Play speed} = \frac{\text{Number}}{60} \times \text{normal speed}$$

The following table shows what speeds are attained under what values:

Number	Speed Increased	Number	Speed Decreased
240	x4	30	1/2
180	x3	20	1/3
120	x2	15	1/4
60	x1	10	1/6

Examples:

1. 30SP MF - 1/2 speed play forward.
2. 180SP MR - x3 speed play reverse.

Stop Marker (SM)

This command will memorize a specific disc location. The specified number is written in a special register. When the disc is being played (in either Play or Multi-Speed mode) the player will execute a Still (CAV) or Pause (CLV) upon reaching the specified location. As soon as it's reached, the register is cleared. The register is also cleared when a Clear or a Reject command is given or you Step through the location. The command is similar to the Auto-Stop function incorporated into the Play command (see Play). Its advantage is that you can execute other commands (Pause, Still, Speed, Multi-Speed) and still have the command active. With the Play command, the auto-stop function is over-ridden as soon as you execute any other command.

Example:

FR 7000SM PL - Marker set to frame 7000. Begin playing.

180SP MF - Execute x3 forward Multi-Speed... still looking for frame 7000.

PL - Back to Play mode until frame 7000 is finally reached.

Video Control (VD)

The Video Control command can turn off the video signal, showing you the blue screen. This is useful when you wish to hear audio alone. Some videodiscs have sound effects compilations and small musical interludes while the accompanying video is not related to the material at all. You could use Video Control to turn off the accompanying video.

When you set the register to 0, the picture is shut off, regardless of what state your player is in. The default setting is 1 (video is on, with the blue screen controlled by the player).

Example:

0VD - Video Switch is off; (the Blue Screen is forced on).

Sample Advanced Command Boxes

Below are several sample command boxes using advanced commands that you could use when setting the button information for a video control button. Beside each is a description of the actions it will produce on your screen. Notice how space is saved within the boxes by eliminating any spaces between a command and its necessary parameter (number). Each of these samples assumes that Key Color on the OPTIONS MENU of your HyperScreen program is set to None.

Show Series of Stills - 2

Video Command
SA KC7 1RA 1DS 1000SE WA3 400SE WA3 SR WA3 0DS KC0 RJ
Press Esc to accept.

This will:
Start player, turn off computer graphics, display frame number on screen, show images at frames 1000, 400, and 399 for 3 seconds each, turn frame display off and computer graphics on, stop player.

Show Video Clip - 2

Video Command
SA KC7 4RA CS 1DS 11PR This is half speed. 30SP FR 500SE 700NF CS 0DS KC0 RJ
Press Esc to accept.

This will:
Start player, turn off computer graphics, turn off cleared user display, print message on line 11, play frames 500-700 at half speed, reset display, stop player.

Chapter Button

Video Command
1DS SA 1000SE 1100PL WA10 CH SA 3SE 4PL WA10 RJ
Press Esc to accept.

This will:
Turn on display, start disc, search for frame/time 1000, play until frame/time 1100, wait 10 seconds, toggle chapter on, jump back to beginning of disc, search for chapter 3, play until chapter 4, wait 10 seconds, stop player.

Key Lock Button

Video Command
1KL 4RA 4PR YOU CAN'T TOUCH ME! WA15 CS 3RA 0KL
Press Esc to accept.

This will:
Turn on Key Lock, turn on the display, set Register A to display user's portion only, go to line 4 and print "You can't touch me!", wait 15 seconds, clear screen, set Register A to its default (3), turn off Key Lock.

MultiSpeed Button

Video Command
SA 1000SE 180SP 1400MF WA10 20SP 1000MR WA10 RJ
Press Esc to accept.

This will:
Start player, search for frame 1000, set speed to 3 times fast, play multi-speed forward until frame 1400, wait 10 seconds, set speed to 3 times slow, play multi-speed reverse until frame 1000, wait 10 seconds, stop player.

Register B Button

Video Command
192RB SA 100SE NF NF NF WA10 NR NR NR WA5 180SP 300MF 0RB RJ
Press Esc to accept.

This will:
Set Register B to turn off both audio and video squelch, start disc, search for frame 100, scan forward 3 times, wait 10 seconds, scan backwards 3 times, set speed to play 3 times as fast, multi-speed forward until frame 300, set Register B to default (0), stop player.


GLOSSARY

CAV Format A videodisc that is formatted using a technique called Constant Angular Velocity. These discs allow single picture viewing and are limited to 30 minutes per side. Some commands are specific to this format. This is also known as standard play format.

Chapters Sections of a videodisc (similar to chapters in a book) which are cited for their relevance to the videodisc as a whole. A play, for example, might have chapters for the beginning of each act. This eliminates the need to memorize large frame or time numbers.

CLV Format A videodisc that is formatted using a technique called Constant Linear Velocity. Although this format does not support single pictures, it allows up to one hour per side of a videodisc. Due to its format, however, some commands do not support CLV discs. Also known as extended play format.

Display Area The area on the screen that the videodisc player uses to display information relevant to the disc, i.e. the Frame number, the Time number, the Chapter number. It also contains the user's portion, an 8 or 11 character tall by 20 character wide section of the screen that you can place text on (see Print, Clear Screen, and Register A under Advanced Commands). This is built into the player itself. See your operating instructions to determine whether your player displays 8 or 11 lines. In order to see the full Display Area, turn off your player and set function switch eight on the front panel to the down position. When you turn the player back on you should see the display area filled with every character it supports. Make sure to turn the player off and set function switch eight back to its default up setting in order to use it normally.



Frames Applicable only to CAV videodiscs, frames are the individual pictures on a disc, similar to frames on a film strip. They can be viewed individually or at speeds many times slower or faster than normal, in either forward or reverse directions.


Register A register can be best thought of as an electronic "box" inside the player where certain values are stored for later retrieval or reference. The speed register, for example, is a "box" that holds the value for determining how fast or how slow the disc will go when Multi-Speed is executed. You can change the value in the "box" using the Speed command and thereby change the rate at which Multi-Speed will play the disc. The contents of this "box" will remain the same unless specified otherwise. Turning off the player restores the original value within a register.

Time Code Applicable only to CLV videodiscs, time code, or more simply time, is the amount of elapsed time from the beginning of a disc. It is specified in hours, minutes, and seconds.


APPENDIX B

Graphic Backgrounds, Clip Art, Fonts, Borders, Sound


Graphic Backgrounds (Disk B, Side 1)




BLUEPRINT




CALENDAR




CITY



CLIPBOARD




CLOSED.BOOK



DESERT


Graphic Backgrounds cont'd.




FOLDER




FRAME




GAMESHOW




GRAPH



LINED.PAPER



NEWSPAPER




NOTECARD




OCEAN


Graphic Backgrounds cont'd.



OPEN.BOOK




SCRAPBOOK




STAGE




US.MAP




RURAL



STACK.OF.BOOKS



TIMELINE



WORLD.MAP

Clip Art



CAT



DOG



FISH



LIZARD



WHALE

Animals



OUTLINE.HOR.LG



OUTLINE.HOR.SM



OUTLINE.VER.LG



OUTLINE.VER.SM



RETURN.LG



RETURN.SM



SOLID.HOR



SOLID.VER



SPECIAL.HOR



SPECIAL.VER

Button.Icons/ Arrows



BROWSING



POINTING.LG



POINTING.SM



STOPPING










THUMBING



























WRITING

Button.Icons/ Hands







Clip Art cont'd.












 BLOCK.DARK	 BLOCK.LIGHT	 POINTING	 SHOWING
 COTTAGE	 THREE.BEDROOM	 STANDING	
Button.Icons/ Home		Button.Icons/ Figures	







 BELL	 BOOK	 EARTH	 FILM.CLIP	 GLOBE
 MAGNIFYNG.GLASS	 MEMO	 MUSIC	 NEWSPAPER	
 SEEING.EYE	 SLIDE	 SOUND	 TELEVISION	
	 VIDEODISC	 VIEWER		
Button.Icons/ Information				

 CALENDAR	 CONTENTS	 HELP.LG	 HELP.SM	
 INDEX	 MENU	 STOP	 ZOOM.IN	 ZOOM.OUT
Button.Icons/ Organization				

Clip Art cont'd.

 RECT.OUTLINED	 RECT.ROUNDED	 RECT.SHADOWED
 ROUND.BUTTON.1	 ROUND.BUTTON.2	 SQUARE.BUTTON
Button.Shapes		

 CITY	 CLOUDY	 COMPASS.ROSE	 FACTORY
 MINE	 RAINY	 SNOWY	 SUNNY
 USA.48.STATES			
		 WORLD.MAP	 X.MARKS.SPOT
Maps			

 COMPUTER	 DISK.3.5	 DISK.5.25	 PICTURE.FRAME
 STILL.CAMERA	 VIDEO.CAMERA		
Miscellany			


Clip Art cont'd.



BABY



BOY.POINTING



CHILD.WITH.DOG



GIRL.WHEELCHAIR



GIRL.WITH.BOOK




MAN



WOMAN

People



CACTUS



FIR.TREE



FLOWER



PALM.TREE



SAGUARO

Plants



BUS



CAR



PLANE



SHIP



TRAIN



TRUCK

Transportation

Fonts (Disk B, Side 2)

future.15

Lyric.18

Orpheum.12

Orpheum.18


Orpheum.24

Plaza.12

Plaza.24

Rialto.18

Borders



BALL.LINE



BAR.DIAMOND




CHECKERS




CIRCLE.BOX

Borders cont'd.




CLASSIC




COMPUTER.PAPER




DECO



MARQUEE




MEMO.PAD



PAWS




PENCILS




PIANO

Borders cont'd.



SCHOOL.BOOK



SHADOW



SPIRAL.1



SPIRAL.2




SPOTS



STACK.OF.PAPER



THUMB.TACKS



TRIANGLE

Sound

BACH.INTRO	FANFARE	MOZART.INTRO
BRANDENBURG	FIFTH	ROCKNROLL
BROWSING	FUR.ELISE	THE.END
CALL.TO.RACES	GREAT.BOOKS	THE.TRUTH
CHARGE	INDIAN.THEME	TRAFFIC
DIRGE	INVENTION.8	VOLGA
EXHIBITION	JESU.JOY	WILLIAM.TELL
FAIRY.MUSIC	MAGIC	YELLOW.ROSE.TXS
		ZARATHUSTRA

Music

BIRD.CHIRPING	FUTURE.LAB.1	MOVIE.BOARD
BUMP	FUTURE.LAB.2	OOPS
BUZZER	HEARTBEAT	PAUSE.2.SECOND
CAT.MEOWING	KNOCKS	PAUSE.5.SECOND
DOG.BARKING	LAB.CRACKLE	PAUSE.10.SECOND
DOODLE.UP	MAGICAL	POINT1
DRUMS	MORSE.CODE	POINT2

Sound.Effects

Sound cont'd.

		TELEPHONE
POINT3	SHOOTING.STARS	TICK.TOCK
POINT4	SIREN	TRAFFIC.SOUNDS
POINT5	STATIC	WIND.HOWLING
QUEEP	SWOOP.DOWN	ZAP
RUSHING.WATER	SWOOP.UP	ZWIT

Sound Effects cont'd.

ATTENTION	SORRY
CONGRATULATIONS	SORRY.WRONG
CORRECT	THATS.NOT.RIGHT
GOOD.WORK	THATS.RIGHT
GOODBYE	THE.END
HELLO	TRY.AGAIN
INCORRECT	VERY.GOOD
PRESENTING	

Speech

Educator's Guide to Software Copyright Policies and Ethics

Scholastic believes educators are committed to protecting the intellectual property rights of software authors and publishers. At the same time, we have heard from many of you that copy protection code often inconveniences or impedes the legitimate use of our software.

Beginning August 1, 1989, we have taken the extraordinary step of publishing ALL new Scholastic software without any copy protection code and have even removed such code from our major products published before that date. For your further convenience and cost savings, we are also offering customized lab packs and site licenses for these products. We hope other publishers will soon follow our lead in saying to educators: "You trust us; we trust you."

The following policies and procedures have been developed to protect the copyrights of Scholastic and its authors while at the same time providing educators with the greatest possible convenience when using Scholastic software. These policies are consistent with the 1987 Statement on Software Copyright issued by the International Council for Computers in Education (ICCE). Relevant sections from that document and a model copyright policy from the New York City Board of Education are included for your reference.

Scholastic Software Copyright Policy

- I. All Scholastic non-copy protected software packages consist of one Archival disk or set of disks, a Legal Copy label for each disk, and appropriate documentation. No back up disk(s) are included since the Archival disk(s) will be the back up(s) once Legal Copies are made.
- II. As with all Scholastic software, non-copy protected programs may be evaluated **FREE** for up to 30 days. During that time, the user **MAY NOT** make copies of any disks or documentation.
- III. If the customer decides to purchase the software, the enclosed Software License and Warranty Agreement **MUST** be filled out and returned to Scholastic.
- IV. The user **MUST** then use the Archival disk(s) to make one and only one Legal Copy of each Archival disk, for use at any one time.
- V. Each Legal Copy disk **MUST** be labeled with the Scholastic Legal Copy label on which the user has entered the serial number provided on the Software License and Warranty Agreement.
- VI. **ONLY** the Legal Copy may be used for educational purposes. The Archival disk **MUST** be stored, to be used again **ONLY** to recopy the program if the Legal Copy becomes defective.

VII. Under **NO** circumstances may the Legal Copy be used to make additional copies.

VIII. Schools needing multiple copies of a Scholastic program **MAY** either buy multiple Legal Copies in the form of Customized Lab Packs or purchase a Site License, which entitles them to make unlimited Legal Copies for use within a designated school.

IX. Under Scholastic's unique LIFETIME WARRANTY, if the Archival disk or the Legal Copy disk itself becomes defective, it may be returned to Scholastic for a free replacement. No questions asked. No shipping or handling charge. However, please note that to be eligible for this Warranty, the customer **MUST** have filled out and returned to Scholastic the Software License and Warranty Agreement.

X. Customers currently owning copy protected versions of titles that will now be published without copy protection code are entitled to purchase non-copy protected Legal Copies at low Customized Lab Pack prices. With such a purchase, the customer may also request the Archival disk(s) to be used to recopy the program, in case of Legal Copy disk failure.

XI. Scholastic programs are **NOT** to be loaded into more than one computer at a time, unless a Network License has been purchased from Scholastic. This restriction includes hard disk based networks, floppy disk based networks, and any and all multi-loading devices.

XII. Many Scholastic programs have been designed to be RAM-resident so that they can be removed from computers equipped with only a single disk drive, freeing the disk drive for graphics, data, or spell checking disks. These programs are **NOT** intended to be multiloaded. We believe multiloading to be an educationally, economically, and legally unsound practice. It wastes valuable instructional time, may limit access to program options that are not wholly RAM-resident, and often leads to premature disk failure. Moreover, it violates the copyrights of our authors and is inconsistent with the rest of our Software Copyright policies which prohibit unauthorized copying, whether the copy is a temporary one (in RAM) or a permanent one (on disk).

We believe the policies listed above will serve the best interests of our customers, our authors, and the field of educational computing.

**Excerpts From The 1987 Statement on Software Copyright:
An ICCE Policy Statement**

The following recommendations and guidelines were approved by the Board of Directors of ICCE in January 1987, after having been developed by the 1986 ICCE Software Copyright Committee

ICCE Suggested Software Use Guidelines

The 1976 U.S. Copyright Act and its 1980 Amendments remain vague in some areas of software use and its application to education. Where the law itself is vague, software licenses tend to be more specific. It is therefore imperative that educators read the software's copyright page and understand the licensing restrictions printed there. If these uses are not addressed, the following Guidelines are recommended. These Guidelines do not have the force of law, but they do represent the collected opinion on fair software use by nonprofit educational agencies from a variety of experts in the software copyright field.

Back-up Copy: The Copyright Act is clear in permitting the owner of software a back-up copy of the software to be held for use as an archival copy in the event the original disk fails to function. Such back-up copies are not to be used on a second computer at the same time the original is in use.

Multiple-loading: The Copyright Act is most unclear as it applies to loading the contents of one disk into multiple computers for use at the same time. In the absence of a license expressly permitting the user to load the contents of one disk into many computers for use at the same time, it is suggested that you not allow this activity to take place. The fact that you physically can do so is irrelevant. In an effort to make it easier for schools to buy software for each computer station, many software publishers offer lab packs and other quantity buying incentives. Contact individual publishers for details.

Local Area Network Software Use: It is suggested that before placing a software program on a local area network or disk-sharing system for use by multiple users at the same time, you obtain a written license agreement from the copyright holder giving you permission to do so. The fact that you are able to physically load the program on the network is, again, irrelevant. You should obtain a license permitting you to do so before you act.

Model District Policy on Software Copyright

The following model policy was developed by the ICCE Software Copyright Committee which recommended that school districts approve a policy along these or similar lines.

It is the intent of [district] to adhere to the provisions of copyright laws in the area of microcomputer software. It is also the intent of the district to comply with the license agreements and/or policy statements contained in the software packages used in the district. In circumstances where the interpretation of the copyright law is ambiguous, the district shall look to the applicable license agreement to determine appropriate use of the software [or the district will abide by their own approved software use guidelines].

We recognize that computer software piracy is a major problem for the industry and that violations of copyright laws contribute to higher costs and greater efforts to prevent copying and/or lessen incentives for the development of effective educational uses of microcomputers. Therefore, in an effort to discourage violation of copyright laws and to prevent such illegal activities:

1. The ethical and practical implications of software piracy will be taught to educators and school children in all schools in the district (e.g., covered in fifth grade social studies classes).
2. District employees will be informed that they are expected to adhere to section 117 of the 1976 Copyright Act as amended in 1980 governing the use of software (e.g., each building principal will devote one faculty meeting to the subject each year).
3. When permission is obtained from the copyright holder to use software on a disk-sharing system, efforts will be made to secure this software from copying.
4. Under no circumstances shall illegal copies of copyrighted software be made or used on school equipment.
5. [Name or job title] of this school district is designated as the only individual who may sign license agreements for software for schools in the district. Each school using licensed software should have a signed copy of the software agreement.
6. The principal at each school site is responsible for establishing practices which will enforce this district copyright policy at the school level.

(Reprinted with permission)

Scholastic recommends that school districts post a summary of the key points of their Copyright Policy wherever computers are in use in district buildings. For example, the New York City Board of Education prints the following information on a large poster that is posted conspicuously in every computer room, and next to computers that are available for staff and student use.

**Copyright Law Restated
New York City Board of Education
Division of Computer Information Services
Office of Technical Assistance and Support
131 Livingston Street
Brooklyn, N.Y. 11201**

SOFTWARE POLICY

1. Duplication of copyrighted software is prohibited, except for a single Archival copy not to be used simultaneously with the original.
2. School computers may not be used to illegally duplicate copyrights software.
3. The school must contact software publishers to obtain written permission and procedures for making back-up and multiple copies, other than a single Archival back-up.
4. The school must obtain written permission from the publisher to download or network programs to other microcomputers.
5. The use of illegally duplicated software, however obtained, is prohibited in all Board of Education facilities.
6. The school must obtain the written permission of the publisher to use the original software and its back-up simultaneously.
7. The Principal of each school is responsible for establishing practices which will enforce this policy on the school level.
8. This policy should be posted conspicuously in every computer room, and next to computers that are available for staff and student use.
9. Violators of this software policy will be subject to disciplinary action.

These regulations are applicable to all Board of Education facilities.

(Reprinted with permission)

INDEX

A

Adding screens 44
APPLE MENU 31

B

Block 81
Border 75-76
Border Color 95
Browse 9, 23, 38-39, 101-104
Browse keypresses 24, 40, 102-103
Browse Options box 99, 102
Browsing from a stack disk 103
Browsing from the menu bar 101
Brush 77
Brush Shape 96
Brush Shape submenu 78, 96
Button 9
Button Type menu 51

C

Choosing a button type 57
Choosing a Text or Graphic Screen 17, 41-42
Clear 53
Clickable buttons 22, 56
Clicking 9, 14
Clip Art
 Coloring 87
 Flipping 49
 Libraries 86
 Saving 49
 Selecting a piece 86
 Switching between opaque and transparent 52
Color Palette 94
Control Keys for graphic tools 78-84, 86
Copy 51
Correcting mistakes 99-100
Create Stack Disk 19, 31
Cut 50

D

Delete Screen 44-45
Delete Stack 37
Disk Menu Box 28-29
Disk Space 46
Do On Opening buttons 22, 56

E

EDIT MENU 50
Escape key 28
Export Screen Image 48

F

FILE MENU 35
Find Files 29-34
Flood Fill 84
Folders 29
Frame 80-81

G

Graphic Background 88
Graphic Font 97
Graphic Tools 77-89
Graphics programs and utilities 89

H

Help 15, 27
Home Screen 9
Home Stack 9, 26, 31

I

Import Text 92
Ink Color
 Color Palette 94
 Selecting 94

J

Joystick 14, 33

K

Keyboard mouse 33

L

Legal Copies 11
Link to Screen button 8, 21, 58
Link to Stack button 8, 21, 61-62
Loading the Program 13

M

Match pattern guidelines 69-70
Menu bar 30
Modem Port 137
Mouse 14, 33
Moving a button 54
Multi-button 8, 21, 62-64

N

New Screen 41
New Stack 16, 19, 35-37
No Match Screen 71
Non-clickable buttons 22, 56

O

Open Screen 43
Open Screen menu 60
Open Stack 37

Opening Transition 76-77
OPTIONS MENU 93
Oval 83

P

Pelican Graphics Converter 89
Pen Line 79
Pen Width 96-97
Pen Width submenu 79-80, 96
Pointer Setup 33-34
Pop-up Text button 8, 21, 64-65
Preview 9, 22, 47
Previous Screen 60
Print Screen 48
Printer Setup 31-33

Q

Quit 49

R

Resize buttons 54
Ring 82-83

S

Save Screen 23, 45
Scanner 10
Selecting 14
Set Button Info 54-56
Set Buttons 20, 33, 53
Set Entry Blank 72-73
Sound 57
Sound/FX button 8, 21, 66-68
Stack 9
Stack Design Chart 9, 105
Stack End 60
Super Serial Card 138

T

Tab key 29, 36
Text Background 98
Text editing commands 90
Text Entry button 8, 22, 68-72
Text Font 98
Text fonts submenu 90
Text Screen arrows 92
Text Screen rounded-corner button box 91
Text tools 89-93
TOOLS MENU 74
Tutorial 104
Type 84-85
Type font submenu 85-86, 97

U

Undo 50

V

Video Control Appendix 137-155

Video Control button 8,22, 73-74

Video control commands 141

Video Equipment 137

Video Key Color 95-96

Video Overlay Card 139-140

Video switches 138

Y

Yes Match Screen 70

Scholastic ***HYPERSCREEN™***

TEACHING GUIDE

by George Brackett

Design and Programming	George Brackett
Reference Guide Author	Ellen Geist
Tutorial Author	Donna Miller
Video Control Author	Miguel Chavez
Teaching Guide Authors	Jennifer Howland, Ellen Baru
Graphics	Angela Greene
Published by	Scholastic Software 730 Broadway New York, NY 10003
Publisher	Peter Kelman
Director of Product Development	Philip Miller
Editorial Director	Amy McKinley
Project Editor	Debra Weinberger
Contributing Editor	Sara Anne Romanelli
Managing Editor	Pamela Lawson
Production Editor	Chuck Wahrhaftig
Print Production	Rick Scarbrough
Art Director, Print	Jenny Grant
Additional Support	Rachel Auslander
Director of Marketing	Susan Beecher

Scholastic Inc. New York Toronto London Auckland Sydney

Notice: This work is fully covered by the Copyright Law of the U.S. (Title 17 of the U.S. Code) and the Universal Copyright Convention. Unauthorized copying is strictly prohibited.

Software copyright © 1990 George Brackett. Published under exclusive license with Scholastic Inc. All rights reserved. Teaching Guide copyright © 1990 Scholastic Inc. Printed in the U.S. A. Published by Scholastic Inc.

Apple is a registered trademark of Apple Computer Inc.

ISBN: 0-590-82304-3 12 11 10 9 8 7 6 5 4 3 2 1 1 0 1 2/9

CONTENTS

Scholastic HyperScreen Teaching Guide	5
Why Use Scholastic HyperScreen	5
Critical Thinking	5
How to Start	6
Classroom Management	6
Classroom Computer Arrangement	7
Software Needs	7
HyperScreen Hints	7
HyperScreen Quick Starts	8
Ms. HyperHeart	8
News Flash	9
Password to Treasure	10
HyperScreen Curriculum Activities	12
Book Review	12
The Book Review Ad	13
Creating a Food Web	14
Food Web, Extended	15
Vocabulary Builder	16
Vocabulary Quiz	17
Stepping Through Time	18
Stepping Through Time, Extended	18
On Exhibit	20
Math Flash	21
The Scene of the Crime	22
Statistically Speaking	23
Should We Save the Rainforests?	24
HyperScreen Ideas Across the Curriculum	25
English	25
Science	26
Social Studies	27
Mathematics	28
HyperScreen Stack Design Charts	29
Single-screen Stack	30
Chain of Screens	31
Branching Chain of Screens	33
Hub Screen with Linked Screens	35
Linked Hub Screens	36
Linked Web of Screens	38

SCHOLASTIC HYPERSCREEN TEACHING GUIDE

Why Use *Scholastic HyperScreen*?

We are constantly bombarded by information—TV pictures, news headlines, catchy jingles, posters, and sirens. Students interact with media from music videos to video games to magazines, sometimes simultaneously—information in a constant and relentless stream. They need ways to organize and retrieve information effectively. *HyperScreen* is an information-organizing tool accessible to students. It promotes active use of information. Using *HyperScreen*, students relate text, images, and sounds in original ways.

Teachers can use *HyperScreen* to create multimedia interactive lessons and presentations organized in stacks for students to browse through, or guide students to construct their own stacks. Teachers of young children can make stacks that present or reinforce curriculum in innovative ways. Teachers of older students can make browsable stacks, and can lead their students to make their own as well. When designing stacks, students decide what information to incorporate and how the information will be retrieved. This makes *HyperScreen* a powerful teaching tool.

Critical Thinking

In the process of planning and creating a stack students develop these skills:

- Problem solving.
- Setting goals.
- Analyzing ideas.
- Synthesizing ideas.
- Thinking in a non-linear way.
- Organizing information.
- Thinking visually.
- Locating, gathering, and evaluating information.
- Making decisions.
- Thinking metaphorically.
- Developing a point of view.
- Designing.
- Testing.
- Revising.

In the process of planning and creating stacks together, students learn to be productive members of a group.

How to Start

This Teaching Guide assumes you have worked with the program and have completed the Tutorial on page 104 of the User's Guide or made a stack or two of your own. If not, turn to the Tutorial, or to the Quick Guide on page 19 of the User's Guide. Once you have become familiar with *HyperScreen*, decide how you want your students to use this program. Will they be browsers, designers, or both?

If you want your students to browse stacks only, then your preparation will be limited to stack design and a brief explanation of how to browse. However, if you want the students to design stacks, then you will need to introduce the individual features of *HyperScreen*.

You can teach *HyperScreen* techniques and assign starter projects without having explored every aspect of the program. Once you teach students the basics, they will quickly take off.

As you begin designing *HyperScreen* stacks, suspend your curriculum needs to allow yourself time to get used to the program. Make a *HyperScreen* Quick Start activity. (See pages 8-11 of this Guide.) As you make the Quick Start stacks, you will start to see how *HyperScreen* works and relates to your curriculum. Also, see *HyperScreen* Curriculum Activities beginning on page 12 and *HyperScreen* Ideas Across the Curriculum beginning on page 25 for ways to use *HyperScreen*.

Classroom Management

Grouping Students to Design Stacks

When organizing your students for a *HyperScreen* project, decide whether to have individual or group projects. You may choose to have students work as a committee with each person taking on a specified job such as structural designer, artist, researcher, writer, or reviewer. Students will go through the following cycle of tasks: planning, creating, testing, and revising.

During the planning stage, encourage your students to brainstorm and outline their project. Ask them to explore these questions: What is the object of your stack? Who is your audience? What information is going into your stack? Do you need to do research? How are you going to organize it? What graphics, text, and sound do you need? How will your audience retrieve the information?

If students have many sessions in which to complete their work, they can create complex stacks. If their time is limited, they may have to streamline their stacks. If students want to put a lot of information into a *HyperScreen* creation, they can divide the work into different categories and link stacks together.

As students create a stack they will move between designing, revising, and testing. Have students share a stack-in-progress to see whether it works as they planned.

Classroom Computer Arrangement

With One Computer

One Stack

The whole class works together to design a stack. Divide the work involved among pairs of students. Then students can take turns working at the computer.

Multiple Stacks

Students are asked to work individually, in pairs, or in small groups to complete their stacks.

With Multiple Computers

Even though you may have many computers available, you may choose to have students work in groups on some tasks. This program lends itself to committee work.

NOTE: When creating browsable stacks for your students, keep in mind that if you have one computer you will want to make short stacks for them, while if you have multiple computers your stacks can be longer.

Software Needs

When using *HyperScreen*, you will need the *HyperScreen* disk package which includes Graphic Backgrounds, Clip Art, Fonts, Borders, and Sound as well as blank disks. Optional disks include *Slide Shop™*, *Super Story Tree™*, *Scholastic Graphic and Sound Booster Packs™*, compatible word processors and graphics programs, and ProDOS disks on which to save original artwork.

See page 16 in the Getting Started section of the User's Guide for more information about disk management.

Below is a useful summary of information and tips on using the program. You may want to copy or share this information with your students.

HyperScreen Hints

Stack Design

Think through a stack design before creating a stack using *HyperScreen*. Make notes using a chart or map of the stack. When designing a screen, think about where you want to go from that screen and design buttons to reach that destination. To avoid dead ends and endless loops, careful planning of overall stack design is recommended. See the Stack Design Charts on page 105 of the Tutorial in the User's Guide and on pages 29-38 of this guide for ideas.

Screen Design Questions

When creating a stack, keep your audience in mind. For whom is the stack designed? How much information can be put on a screen without overwhelming the user? Should the buttons be visible or invisible to the user?

Button Visibility

When planning buttons on a screen, consider whether to mark them clearly or hide them. Factors to consider are the age of the user and the purpose of the stack. For example, if you want the user to move easily from one screen to the next, it makes sense to have a clearly marked Link to Screen button. However, if the design is a haunted house, for instance, and the user is meant to stumble on a secret passage, then the button should be hidden.

Naming

There is a lot of information to name in *HyperScreen*—stacks, screens, and original clip art. Naming is an important organizational skill. Choose names that are functional. When names are clear, it's easier to maneuver back and forth between screens when designing a stack.

Disk Space

Since a 5.25-inch disk fills up quickly, it is advisable to put only a few stacks on a disk. It's possible to fit more stacks on a 3.5-inch disk. Have extra stack disks available, especially when first using *HyperScreen*.

Disk Full Message

At times you will be working on a screen and find you are unable to save it because the disk is full. To get around this keep a number of ProDOS disks handy. Insert a ProDOS disk and choose Export Screen Image from the FILE MENU on the menu bar to save a screen and later import it as a graphic background. Any buttons that have been created will not be saved on the exported image, so a screen should also be saved with the Save Screen option if you wish to save buttons.

Superscript or Subscript

If you are using math or science symbols, choose a Graphic screen and select Type. Pressing Esc moves the cursor to the desired location for a superscript or subscript.

HyperScreen Quick Starts

As a way to introduce yourself and your students to *HyperScreen*, try one of these quick ideas. Make a stack disk with these stacks on it and make copies so students can browse through these activities at several computers simultaneously. If you need more instructions on using any of *HyperScreen*'s features as you create your stacks, consult the appropriate section of the Reference Guide in the User's Guide.

Ms. Hyper Heart

This stack, will include an advice-column letter with a problem. Three possible answers to the problem will appear in pop-up text buttons at the bottom of the screen.

In browsing through this stack, students will:

- Use Pop-up Text buttons.


Elements Used to Create a Single-screen Stack

- A typed letter asking for advice.
- Three Pop-up Text buttons containing possible answers to the letter.

Find an advice-column letter with a problem that might interest your students. If you like, write your own letter. Choose three people who will answer this letter. Type their names on the screen.

Use Set Buttons and Set Button Info to make each of the three names into a Pop-up Text button. Type the advice in the appropriate pop-up text windows. Be sure the name of the advice giver appears in each window.

Below is an example of text you might use for this screen.



The names Sneaky Kid, Aunt Agnes, and Ear Doctor are Pop-up Text buttons. Below is the text that will appear when each is clicked.

Sneaky Kid—Hey Rocky, chill out. Tell them you are baby-sitting and go anyway. This is a free country.

Aunt Agnes—Rocky dear, you can stay with me in the city that night. Cousin Frank could take you there and pick you up.

Ear Doctor—Well, Rocky, unless you want to be stone deaf, you'd better watch those decibels. Get earplugs and wear them!

You might want to initiate a class discussion about various other solutions to the problem.

News Flash

This stack will include a Home Screen with catchy news titles linked to screens with news briefs.

In browsing through this stack, students will:

- Use Link to Screen buttons.

Think of catchy news headlines for books or ideas in your curriculum. Below are examples of headlines you might use.


Families Feud, Tragedy Ensues (*Romeo and Juliet*)
King Kills Dad, Marries Mom (*Oedipus Rex*)
Designer Genes (DNA)
Bus Seat Leads to Boycott (Rosa Parks)

Elements Used to Create a Home Screen

- Typed news headlines.
- Link to Screen buttons.

Type in your headlines. After each headline type **Continued**.

Use Set Buttons to make each "Continued" a Link to Screen button. Use Set Button Info to link each "Continued" button to a new screen. You could name the screens Brief1, Brief2, etc.



Elements Used to Create News Brief Screens

- Typed in news briefs.
- Link to Screen buttons.

Type in a news brief to accompany each headline. Type **Home** at the bottom of each screen. Use Set Buttons and Set Button Info to make "Home" a Link to Screen button that links each news brief screen to the Home Screen.

Password to Treasure

This stack consists of a Home Screen with pop-up text riddles. The answer to each riddle is a clue to the password.

In browsing through this stack, students will:

- Find hidden Pop-up Text buttons.
- Use information in the Pop-up Text buttons to decipher a secret password.
- Type a password at a Text Entry prompt and go to an appropriate screen.

Elements Used to Create a Home Screen

- A graphic background, clip art, and original drawing.
- Hidden Pop-up Text buttons with riddles typed into the text windows.
- A written prompt with a Text Entry button set below.


Think of a password. Make up a short riddle for each of the letters in the word.

Design the screen using a graphic background and clip art. Use Set Buttons to make as many Pop-up Text buttons as there are letters in the password. Use Set Button Info for each button to type in a riddle with an answer that is one letter of the password.

Type in a prompt on the screen asking for the password, for example, **What's the word?** Create a Text Entry button near the typed prompt.

Use Set Button Info to enter the password as the exact match. The correct password should take the student to a new screen (Yes Match screen) named Payoff. An incorrect answer should take the student to a new screen (No Match screen) called Noway.

Use Open Screen to work on the two new screens, Payoff and Noway, that are linked to the Text Entry button. Each of these screens should have a Link to Screen button connecting it to the Home Screen. Payoff will be a reward screen containing text and sound effects for a successful solution to the puzzle. Noway will tell users that the puzzle has not been solved and they should try again. You could add a hint to the solution on Noway if you like. Link these screens to the Home Screen.



HyperScreen Curriculum Activities

This section contains stack design activities for specific subject areas. Some lessons are designed so you can choose to have students create a one-screen stack or expand the idea into a larger stack with linked screens. Try one or more of these lesson formats, using material covered in your curriculum.

Book Review (a Single-screen Stack)

Curriculum Area English
Grade Level 6th and Up

In designing this stack, students will learn:

- To introduce books by a variety of authors.
- To identify the main idea of a story.

Buttons Used

- Pop-up Text button.

Materials


- Single-screen Stack Design Chart on page 30 of this Guide.

Introducing the Activity

Have students create *HyperScreen* stacks to share books they've read. Each student should think about the main idea of the book he or she has just read and write it down.

Screen Design Instructions for Students

Choose a Graphic screen and opening transition, and decide how to arrange information about the book on the screen. A simple way might be to type the title of the book and put a frame around it. This could be made into a Pop-up Text button. For this stack, the graphic backgrounds from the *HyperScreen* library might also be helpful.



Type the main idea of the book in the Pop-up Text box. Summarize the idea concisely. Keep in mind that the window is limited to 109 characters, including spaces.

Extending the Activity

After book review screens have been created, share them by having the whole class view the stack or stacks on a large monitor, or have students take turns viewing the stacks.

The Book Review Ad (Hub Screen with Linked Screens)

Curriculum Area English
Grade Level 6th and Up

In designing this stack students will learn:

- To develop a book review as an ad that includes a plot summary, description of the main character, setting, and an opinion.

Buttons Used

- Link to Screen button.

Materials

- Books reviewed.
- Hub Screen with Linked Screens Design Chart on page 35 of this guide.


Introducing the Activity

Students should discuss which books to review and which format to use for their stack.


Screen Design Instructions for Students

The following are two possible ways to create a book ad.

1. Create a Home Screen (either a Text or Graphic screen) that is an ad for the book with buttons linking it to other screens. Each connected screen would be a Text screen describing a different aspect of the book. Below is a sample of how your Home Screen might look.



2. Create a Home Screen advertising different books. Each book would be a Link to Screen button connected to a Graphic or Text screen with details about the book.



Creating a Food Web (Single-screen Stack)

Curriculum Area Science

Grade Level 6th and Up

In designing this stack, students will learn:

- The elements of a food web.
- How to construct a model of a food web.

Buttons Used

- Pop-up button.
- Sound/FX button.

Materials

- Reference materials on eating habits of various organisms in a food web.
- Single-screen Stack Design Chart on page 30.

Introducing the Activity


Discuss the elements of a food web. Have students research the eating habits of the organisms in a food web.

Screen Design Instructions for Students

On a Graphic screen show the following elements in a food web:

- Producer.
- Primary Consumer.

- Secondary Consumer.
- Scavenger.



Create a Pop-up Text button with text describing each element. If desired, add a Sound/FX button that operates when the screen is opened (a Do On Opening button).

Food Web, Extended (Chain of Screens)

Curriculum Area Science

Grade Level 5th and Up

In designing this stack students will learn:

- To elaborate a model of a food web.
- Graphic mapping of a food web.

Buttons Used

- Pop-up button.
- Sound/FX button.
- Link to Screen button.

Materials

- Reference materials on eating habits of animals
- Chain of Screens Design Chart on page 31.

Introducing the Activity

Discuss extending the single-screen food web stack by linking it to new screens for each element.

Screen Design Instructions for Students

On the Home Screen described in the Creating a Food Web Stack, add a Link to Screen button. Name the new screen Producer and illustrate the screen. Add a Link to Screen button and name the next new screen Primary Consumer. Illustrate the Primary

Consumer screen and add a Link to Screen button, naming the next new screen Secondary Consumer. Illustrate the Secondary Consumer screen and add a Link to Screen button calling the next new screen Scavenger. Finally, illustrate the Scavenger screen and add a Link to Screen button taking the user to the Home Screen.

To keep successive screens consistent you can import the graphic images directly by selecting Graphic Background from the TOOLS MENU and selecting the appropriate screen from the Stack disk, or you can export the graphic screens as outlined below:

1. Create and save the Producer screen as an exported graphic called Producer (select Export Graphic Screen from the FILE MENU) on a ProDOS disk. After adding buttons, save the screen on your stack disk. Then open the Primary Consumer screen.
2. Select Graphic Background from the TOOLS MENU, import the Producer graphic, draw the primary consumers on it, and export this screen as a graphic called Primary Consumers. Add buttons and save the screen on your stack disk. Then open the Secondary Consumer screen.
3. Select Graphic Background, import the Primary Consumers screen, draw the Secondary consumers on it, and export this graphic screen called Secondary Consumers. After adding buttons to the screen and saving it, open the Scavenger screen.
4. Select Graphic Background once again, import the Secondary Consumer screen, and draw the scavengers on it. Because this is the last screen in the chain, don't export it, but be sure to add a Link to Screen button that will link the user to the Home Screen.

Vocabulary Builder (Single-screen Stack)

Curriculum Area All Subject Areas
Grade Level 5th and Up

In designing this stack, students will learn:

- New vocabulary words and definitions.

Buttons Used

- Pop-up button.
- Sound/FX button.

Materials

- Vocabulary words and definitions to be learned.
- Single-screen Stack Design Chart on page 30.

Introducing the Activity

Have students create a *HyperScreen* stack to help them learn their new vocabulary words.

Screen Design Instructions for Students

On the Home Screen, type the vocabulary words. Under each word, write a sentence using the word. Use Set Buttons to make each word a Pop-up Text button and use Set Button Info to type in a definition of the word to appear in the Pop-up Text window.

Vocabulary Quiz (Branching Chain of Screens)

Curriculum Area All Subject Areas
Grade Level 6th and Up

In designing this stack, students will learn:

- How to design and prepare a vocabulary quiz.

Buttons used

- Pop-up Text button.
- Sound/FX button.
- Link to Screen button.
- Text Entry button.

Materials

- A completed Home Screen vocabulary stack.
- Branching Chain of Screens Design Chart on page 33.

Introducing the Activity

Building on the idea of a single screen from which students can learn definitions of vocabulary words, have students link a quiz screen to the vocabulary screen. Students might learn the definitions of words or master simple facts from the Home Screen, then go to the quiz screen to test themselves.

Screen Design Instructions for Students

Add a quiz Link to Screen button on the Home Screen. Name the new screen Quiz and make it a Text screen.

Write a definition on the Quiz screen for each vocabulary word that appears on the Home Screen, using Set Buttons to make each definition a Text Entry button. Choose Set Button Info. Next to "Match:" type the vocabulary word. Next to "If Yes:" type **Congrats**. Next to "If No:" type **Home**. Set an Entry Blank below each vocabulary definition.

When browsing the Quiz screen, the user clicks on a definition, a prompt appears, and the user types in a vocabulary word. If the user is right, a congratulatory screen will appear. If the user is wrong, he or she will be linked to the Home Screen to study the word and definition again.

Create a reward screen (a Text screen) for correct answers. Add a Sound/FX button with music or speech. Link to Screen buttons could return the user either to the Quiz or to the Home Screen.

Stepping Through Time (Single-screen Stack)

Curriculum Area All Subject Areas
Grade Level 5th-12th

- In designing this stack, students will learn:
- To research a 10 year period of history.
 - To select main events of particular interest to them.

- Buttons Used
- Sound/FX button.
 - Pop-up Text buttons.
 - Multi-button.

- Materials
- Encyclopedia, *Guinness Book of World Records*, newspapers, magazines, and other periodicals.
 - Single-screen Stack Design Chart on page 30.

Introducing the Activity
Have the students design an interactive timeline of major historical events that occurred during the first 10 years of their own lives. The students should collect these historical items from a wide variety of sources.

Screen Design Instructions for Students
Use the graphic tools to design a 10-year timeline on the Home Screen. The years should be clearly marked. Use Set Buttons to make each year a Pop-up Text button. Use Set Button Info to type in an historical item for that year. Be sure to include the date in the text window as well.

Now create a Sound/FX button. Mark the button area with graphics or words. Then go to Set Button Info, choose a Sound/FX button type, and select a piece of music, speech, or sound. This should be a Do On Opening button.

Finally, design a Multi-button enabling users to read the timeline facts by flipping through the Pop-up Text buttons. Listing the Pop-up Text buttons in the Multi-button in a specific order allows the user to browse through facts in that order. Try a variety of Multi-button list arrangements.

Stepping Through Time, Extended (Hub Screen with Linked Screens)

Curriculum Area All Subject Areas
Grade Level 5th - 12th

- In designing this stack, students will learn:
- To elaborate details through text and graphics.

- Buttons used
- Sound/FX button.
 - Pop-up Text button.
 - Link to Screen button.
 - Text Entry button.
 - Multi-button.

- Materials
- A timeline (single-screen design described above).
 - Historical resources
 - Hub Screen with Linked Screens Design Chart on page 35.

Introducing the Activity
The students will add a chain of screens to their timeline. Have them decide which incident or person on their timeline interests them most and outline a series of screens for that topic.

Have them research the topic and plan their chain of screens. Since they will be linking Text and Graphic screens, they should designate each screen in their outline as one or the other. A story about an incident or person fits easily into this chain format, but they might use other constructs, such as a series of quotes from a person, the background of an event, or different views of the same occurrence.

Screen Design Instructions for Students
Use the graphic tools to design a Link to Screen button on the timeline Home Screen from the previous single-screen stack. Link this to a new screen. Develop a strategy for naming screens. For instance, in choosing to write about the Space Shuttle, a simple Space1 would probably work better than Spac.Shut. as a title.

Next, set up a series of linked screens. Choose Open Screen from the FILE MENU and open the newly named first screen. Fill the first screen with information, and then link it to the next screen with a Link to Screen button. Keep screens simple at first to concentrate on the flow of screens. Once the travel structure is in place, go back to each screen and fill in more details.

Once the basic screen links are in place, add Pop-up Text, Sound/FX, Text Entry, and Multi-buttons. The following are some suggestions for how to use buttons in this chained series of screens.

- Sound/FX For introductory music, create a Do On Opening button.
To create theme music, make the button clickable, and not a Do On Opening button.
- Text Entry Write review questions about the timeline.
- Pop-up Text Make key words on each screen clickable buttons that present facts in pop-up text windows.

Multi-button Group all the key word Pop-up Text buttons together.

On Exhibit (Linked Hub Screens)

Curriculum Area Social Studies
Grade Level 6th and Up

In designing this stack, students will learn:

- To research and organize information about artifacts from a particular historical period.

Buttons Used

- Pop-up button.
- Sound/FX button.
- Link to Screen button.
- Multi-button.
- Link to Stack button.

Materials

- Reference materials on artifacts from a specific time period.
- Linked Hub Screens Design Chart on page 36.

Introducing the Activity

Discuss the fact that historians often study a large number of artifacts when surveying a particular historical period. Students will create a *HyperScreen* museum exhibit to organize information about selected artifacts.

Screen Design Instructions for Students

The overall design of this stack is a series of hub screens. From each hub, create linked screens that expand on it. Think of each hub as a room in a museum exhibit hall. Place two or three artifacts in each room and link each artifact to a screen describing it. On each artifact description screen create a Link to Screen button connecting the user to the hub screen. Another Link to Screen button should link each hub screen to the next hub screen or room in the museum.

Home Screen:

Use graphic tools to create a museum front with banners containing the name of the museum and the exhibit.

The front door of the museum might be a Link to Screen button that connects to the first exhibit room. Name the new screen Room 1.

Room 1 Screen:

Make Room 1 a Graphic screen. Place two or three artifacts, such as a mummy case, a cartouche, and a canopic jar in the room, using clip art or graphic tools to draw the

artifacts. Each artifact should be a Link to Screen button. On the linked screens, type in information about each artifact. Also create a Link to Screen button connecting to Room 2.

Design a mummy screen as a Text screen describing mummy cases. This screen might have a Sound/FX button that would play upon opening. Add a Link to Screen button connecting the user to Room 1. Design cartouche and canopic jar screens in the same way as the mummy screen.

Room 2 Screen:

Choose a Graphic screen for Room 2 and select a few more artifacts, for example, statues of the gods Osiris, Isis, and Horus. On this screen create Pop-up Text buttons that provide descriptions of each artifact. A Multi-button might also allow the user to click through these Pop-up Text buttons. Finally, create a Link to Screen button connecting to the last room, Room 3.

Room 3 Screen:

Create a Text screen containing a brief quiz on the artifacts, with a question for each artifact. Use a Text Entry button for each question to create a blank so that users can write their answers. For each question, create a congratulatory screen that appears if the answer is correct. If the answer is wrong, the user should be linked to a screen containing more information for help in answering that question. Add Link to Screen buttons that connect to Room 3 or Home.

Math Flash (Single-screen Stack)

Curriculum Area Math
Grade Levels 6th-12th

In designing this stack, students will learn:

- To define specific mathematical terms.

Buttons Used

- Sound/FX button.
- Pop-up Text button.
- Multi-button.

Materials

- Math texts.
- Single-screen Stack Design Chart on page 30.

Introducing the Activity

In this activity the students will prepare math fact screens. First have them decide which math facts or definitions they would like to study.

The students can choose math terms such as *pi*, *hypotenuse*, *imaginary number*, or *integer*. Each of these terms can be made into a Pop-up Text button, with the definition as the pop-up text. Students might also write the definition of each term on the screen and have the terms pop up.

If the students prefer to present math problems or algebraic formulae, then a whole or partial solution to each problem could be presented in a pop-up text window.

Screen Design Instructions for Students

Create a math facts Home Screen using a Text or a Graphic screen. Choose up to 10 math facts or math ideas to present on the screen. Position these facts so a button area can be designated on or near each fact. Create a Pop-up Text button for each fact. Design a few Multi-button areas on the screen. First decide how the facts in the Pop-up Text buttons should be listed in the Multi-button. The facts could be listed in order from the easiest to the most difficult, or staggered in difficulty.

Sound effects could be used effectively on this screen. Create a Sound/FX button, then use a Multi-button to intersperse Pop-up Text fact buttons with the Sound/FX button so the user hears a sound interlude between facts.

The Scene of the Crime (Single-screen Stack)

Curriculum Area All Subjects
Grade Level 5th and up

NOTE: While this stack involves a mystery, it can be adapted to help students learn to gather evidence leading to a solution in any subject area, and this can teach them to develop problem-solving skills.

In designing this stack, students will learn:

- To sort through information.
- To select clues leading to a solution.

Buttons Used

- Sound/FX button.
- Pop-up Text button.
- Multi-button.

Materials

- Mystery books.
- Mystery movies on videotape.
- Single-screen Stack Design Chart on page 30.

Introducing the Activity

Discuss mystery films or television shows students have seen. Have them outline a mystery plot. They should select five clues from one scene of a mystery. They may then design a Home Screen with these clues hidden. Information about the clues will

be retrieved through Pop-up Text buttons and Sound/FX buttons. Have students think about how mystery writers use sounds as clues such as a hollow tap, the creak of a board, a scream, or a gunshot.

Screen Design Instructions for Students

Draw a scene-of-the-crime Home Screen on a Graphic screen or use a graphic background. Use clip art or original art to plant the clues the user will uncover.

Decide where the clues should be arranged and then use Set Buttons to position buttons on the screen. The clues could be Sound/FX as well as Pop-up Text buttons. Hide buttons by blending them into the scene so that the sleuth must poke around to find the information. As in any good mystery, add misleading clues, thus challenging the logical powers of the observer.

After setting buttons, use Set Button Info to type in pertinent facts about each clue. When creating a Pop-up Text button as a clue, label the information so that the sleuth knows to which button the text window refers. This is especially important when the user flips through a series of Pop-up Text clues using a Multi-button.

Statistically Speaking (Linked Web of Screens)

Curriculum Areas Math, Social Studies
Grade Level 5th-12th

In designing this stack, students will learn:

- To plan and conduct a survey.
- To tally up survey results.
- To analyze results and display them as charts or graphs.

Buttons used

- Link to Screen button.
- Sound/FX button.
- Pop-up button.

Materials

- Examples of charts, graphs, and pictograms.
- Examples of surveys and opinion polls.
- Linked Web of Screens Design Chart on page 38.

Introducing the Activity

Students will write up a questionnaire, administer it, and tally up the results. Have students decide on four questions to ask a group of people. Students will then report the results of their survey interactively. The following are some ideas for questions:

Current-events opinion poll—How do you rate the president's performance in these areas: the economy, social services, foreign policy, education?

A past-events opinion poll—What do you think were the four major events in the 19th century?

A cultural opinion poll—What are your five favorite movies, books, works of art, and songs

Screen Design Instructions for Students

The Home Screen is a one of four similar screens containing survey results. Draw one of the survey result graphs on the Home Screen and add three Link to Screen buttons on each screen, connecting them to each of the other screens.

Draw in the results of each of the three remaining questions on Graphic screens and use three Link to Screen buttons connecting the screens. For this activity, the graph paper, notecard, or clipboard graphic backgrounds from the *HyperScreen* library may be useful.

Extending the Activity

Have students use Pop-up Text buttons within each survey screen to give written information about the graphs.

Have students add a Link to Screen button to each of the survey screens connecting it to a Text screen which explains background, administration, and results of the survey.

Should We Save the Rain Forests? (Hub Screen with Linked Screens)

Curriculum Area Science/Social Studies

Grade Level 6th and Up

In designing this stack, students will learn:

- Information about rain forests.
- Different points of view surrounding the survival of the rain forest.

Buttons used

- Link to screen.

Materials

- Magazines and Newspapers with articles about the rain forests.
- Hub Screen with Linked Screens Design Chart on page 35.

Introducing the Activity

Have students discuss the rain forests by collecting articles from magazines and newspapers and analyzing the point of view of each article.

Screen Design Instructions for Students

Design a title screen presenting this problem: A large cooperative cattle farmer funded by a major U.S. fast-food chain wants to clear 20,000 acres of rain forest in Belize. However, there is opposition from various environmental groups around the world. One way of handling this subject might be to create a screen representing a protest rally. Half the screen might be devoted to those who are in favor of cutting down the forests. The other half would show those against clearing the forests. Link to Screen buttons could connect screens on which each group of protesters "states" their viewpoints.

On each viewpoint screen, Link to Screen buttons could connect to the opposing viewpoint screen as well as the Home Screen.

***HyperScreen* Ideas Across the Curriculum**

Here is a list of ideas that lend themselves to *HyperScreen* stacks. They are organized according to subject areas: English, Science, Social Studies, and Math.

English

***HyperScreen* Book Reviews**

Introduce titles by a particular author. Have students make a Home Screen with titles and buttons linked to other screens containing information about the books.

Present books of a particular genre, such as a stack of biographies or mysteries.

Have the class create a stack of book reviews focused on opinions of books.

***HyperScreen* Literature**

HyperScreen is an easy way to have students work with point of view. Students might present a character's dilemma. Then students can create screens in which other characters in the book describe how the problem should be solved.

Have students design a stack to illustrate a sequence of events in a story.

Make a stack of students' favorite sections of a book.

Have students set up a stack as an interview of authors or literary characters.

Students can create their own interactive graphic adventure stories.

***HyperScreen* Writing Workshop**

Have students create a short story or play with *HyperScreen*.

Students can create a cartoon story stack.

You can make a "notebook" stack collection of words, phrases, or sentences that show an interesting use of language.

Have students gather favorite beginnings of books and make a stack of these opening sentences or paragraphs.

Develop an anthology stack for your students of class poetry or poems by favorite authors.

HyperScreen Tutorials

Create a vocabulary stack for your students of synonyms, antonyms, or analogies.

Make a grammar tutorial for your students using a game-show format. For example, have a stack that contains grammar errors. Create linking screens or pop-up text to show the rules of correct usage.

Develop a spelling, punctuation, or capitalization tutorial for your students.

Science

HyperScreen Life Cycles or Processes

Make a stack to show your students the development of a frog, butterfly, or salmon.

Show your students the evolution of the horse in a series of screens.

Explain the process of photosynthesis to your students within a series of screens.

Show the organs of the human body on a screen linked to screens with close-ups of organs.

HyperScreen Diagrams

Show the roles of major plant parts such as roots, stems, leaves, and flowers in a series of screens.

Create a stack illustrating the various layers on a cross section of the earth.

Create a stack describing the three basic rock types formed in the earth: sedimentary, metamorphic, and igneous.

Create a periodic table of elements.

Develop a timeline for scientific discoveries and list names of scientists and their discoveries.

HyperScreen Reporter

Use a weather map to show how weather systems move across the earth's surface.

Develop a stack about an endangered animal.

Have students list air pollutants and how they affect the environment.

Create a stack about the harmful effects of storing hazardous and toxic substances in the soil.

Social Studies

HyperScreen Timelines

Have students design a 10-year family timeline with incidents gleaned from family lore.

Have students select a period of their lives. They can make primary source Pop-up Text buttons of their personal reminiscences.

Have students create a timeline of a historical period that you are studying.

Have students choose a certain period of a family member's life and collect stories and remembrances from him or her.

Have students create a timeline of a historical figure with significant events in that person's life.

Have students create a five-year timeline of two famous people who lived concurrently. Divide each year into two Pop-up Text button areas, one for each person. Use a Multi-button to pair the year buttons together.

Have students design a timeline of one year, marking the time in months rather than years.

HyperScreen Mysteries

Create an archaeological dig stack. Raise the question, What am I? Have a screen with clues about a particular artifact. You might note the variety of ways archaeologists put clues together to identify an object.

Develop a stack of famous historical figures. Present clues to compare two people who claim to be the same person. Students will find the impostor by carefully observing the clothes, mannerisms, and speech of each person.

HyperScreen History

Develop a stack of important events of a specific time period, such as the Civil War, World War 1, the Depression, or the Sixties.

Have students illustrate and describe the branches of the U.S. government using one or more stacks.

Have students compare and contrast two forms of government, such as democracy and communism in one or more stacks.

Have students create a stack displaying the process of how a bill becomes a law.

Mathematics

HyperScreen Math Tutorials

Make a word-problem helper stack. Create a series of screens showing the steps necessary to solving a word problem.

Attach two equations to one math problem and have the user determine which one is correct.

Attach multiple choice answers to a series of math problems. Use a format similar to SAT and PSAT tests.

HyperScreen Tables and Graphs

Have students design a table comparing the literacy rates in various countries.


Have students create a stack illustrating the amount of rainfall during the year in a particular region.

HyperScreen Stack Design Charts


This section of the Teaching Guide will take you through the construction of several HyperScreen Stack Design Charts which can be used for a variety of stacks in different content areas. The charts listed here are just a sampling of the stack designs possible with *HyperScreen*. Accompanying each chart is an example of how it might be filled in using one of the Teaching Guide activities.

Single-screen Stack Design Chart

The single-screen stack is one of the simplest structures you can use—a single screen with Pop-up Text boxes. Single-screen stacks could contain Sound/FX buttons as well as Pop-up Text. You might use Multi-buttons to arrange the order of Pop-up Text and/or sound. This basic stack works well for beginning *HyperScreen* users or younger students.




Use the Single-screen Stack Design for the **Creating a Food Web** activity as in the sample chart below:




Chain of Screens Design Chart

The chain of screens is a simple stack design in which one screen is linked to another in a sequence using Link to Screen buttons. Individual screens could contain Pop-up Text, Sound/FX, and Multi-buttons. You might use this design for more complex stacks by having screens connect to the Home Screen, to each other, or even to another stack as shown with the dotted lines. A Link to Screen button that is last on a Multi-button list could link the screens.




Use the chain of screens design for the **Food Web, Extended** activity as in the sample chart below:




Branching Chain of Screens Design Chart

This stack design is similar to the chain of screens, but in this design screens branch using Text Entry buttons. You could also create branching by setting up two Link to Screen buttons on a single screen and having the user choose a button.




Use the branching chain of screen designs for the Vocabulary Quiz stack as in the sample chart below:




Hub Screen with Linked Screens Design Chart

This more complex stack design uses a central screen, the Home Screen, as a Hub Screen connected to several screens or chains of screens. Link to Screen buttons connect the screens to the hub. This requires several Link to Screen buttons on the hub screen.




Use the Hub Screen with Linked Screens Stack Design for the Stepping Through Time, Extended activity as in the sample chart below:




Linked Hub Screens Design Chart

This is a complex stack design using a series of Hub Screens connected to each other with Link to Screen buttons. Several screens radiate from each hub, connected with Link to Screen buttons.




Use the Linked Hub Screen Design for the **On Exhibit** stack as in the sample chart below:




Linked Web of Screens Design Chart

In this stack design, each screen is connected to all of the other screens using Link to Screen buttons. The user could choose to link to any of the screens in the stack from any other screen. As in the other stack designs, you could use Pop-up Text, Sound, and Multi-buttons on your screens as well.



Use the Linked Web of Screens for the **Statistically Speaking** activity as in the sample chart below:



Create your own multimedia library with multimedia software from Scholastic

Scholastic Slide Shop™

The remarkably versatile multimedia software that gives everyone new and exciting ways to communicate information and ideas

Teachers create dynamic, interactive computer "slide" presentations to introduce new subject areas. Administrators produce multimedia announcements for daily activities and special events, and prepare presentations for faculty or Board of Education meetings. Students easily and creatively design multimedia reports. And everyone has fun with "slide mail"—animated greeting cards or letters that friends can run on their own compatible computers.

Slide Shop's versatility is also evident from the variety of its multimedia output. Self-booting disks will run on any compatible computer without needing the program disk. Screens can be copied onto overhead transparencies. Print-outs of screens can be in color or black and white. Presentations can be transferred from disk to videotape. Even title sequences or other screens can be spliced or overlaid onto full-motion video (overlays require the Apple II Video Overlay Card).

Other special features include:

- Pull-down menus and prompts that make the program easy to use
- Large collection of clip art, decorative borders, and type styles
- Huge library of music, sound effects, and digitized sounds
- Full-featured drawing and paint program
- More than 40 special effects transitions—wipes, dissolves, etc.
- Video key color feature that provides full compatibility with Apple® II Video Overlay Card

Apple is a registered trademark of Apple Computer, Inc.

Super Story Tree™

Adds a whole new multimedia dimension to the best-selling classic Story Tree

Bring multimedia excitement into your classroom with *Super Story Tree*. Using the program's powerful tools, students write branching interactive stories with graphics, special effects, and sounds that spark the writer's imagination and pique the reader's interest.

The writer plots his or her story page by page. The story branches out from one beginning to many endings, twisting and turning as the writer selects the page-linking features. A *continue link* takes the reader directly to the next page. A *choice link* gives the reader up to eight alternative paths to follow. A *chance link* sends the reader to one of two different screens. The reader can interact with the story on the screen—complete with all the visual and sound effects—or read the story printed out in a branching adventure format.

Like *Story Tree*, its award-winning predecessor, *Super Story Tree* can be used to integrate writing across the curriculum. In addition to its obvious advantages as a language arts tool, the program is ideal for student reports and teacher lessons in history, social studies, science...virtually any curriculum area.

Program features include:

- Large collection of graphics to give life and luster to presentations
- Drawing tools to create original artwork
- Huge library of digitized sounds, music, and sound effects for mood, drama, and emphasis
- Text fonts in a variety of sizes and styles that add a professional touch to the work
- Special effects page transitions to create intriguing scene changes and interludes
- Special scanner feature enabling handicapped students to participate in interactive stories by pressing the space bar or clicking the mouse when the desired option is highlighted

Scholastic HyperScreen™

The revolutionary program that brings hyper-power to everyone's classroom computer!

At last, here is an easy-to-use program that allows teachers to create self-booting, interactive lessons on the computer.

The teacher builds an interactive lesson screen by screen, using the program's built-in fonts, clip art, and drawing tools. Each screen can be linked by up to 15 "hot spots" or buttons that enable the students to interact with the lesson; they control their own learning by selecting one of the "hot spots." Depending on their choice, they may be sent to the next screen, to a supplemental screen for additional information, or to an entirely new section of the lesson. Students may be asked to enter text in response to a question and then move to one screen or another depending on their answer. Every screen presents new and exciting learning challenges in a stimulating multimedia format. Lessons can even include frames and segments from a videodisc.

Teachers can create and present interactive lessons in a wide range of curriculum areas, such as language arts, social studies, and science. Lessons can easily be tied in with various content areas through *Scholastic Graphics and Sound Booster Packs*. And students can create interactive multimedia reports and presentations of their own.

This unique program's tools and features include:

- On-screen buttons, or "hot spots," that move students through the interactive lessons in a variety of exciting ways
- Self-booting disks that can be used without the program disk—ideal for making multiple copies of lessons, which can then be shared by students and other teachers or schools
- Fabulous creative resources—graphic backgrounds, art, fonts, drawing tools, sound, and special effects—that heighten student interest
- Techniques for testing and evaluating student understanding, including text string recognition—the program's ability to accept and react to typed-in responses to questions
- Option to branch to an external videodisc player and then return to the program

What are they saying about Scholastic multimedia software?

Slide Shop

"It inspires. It encourages creativity and opens up new avenues of personal expression. The more you use it the more you'll want to use it again...has all the marks of a real winner."

Electronic Learning

"There is little doubt that students in every classroom and every curriculum area can make good use of Slide Shop...I cannot emphasize strongly enough what a fine introduction Slide Shop provides to using the computer as a presentation medium."

Classroom Computer Learning

Super Story Tree

"This program, which mixes text, sound, special effects, and art, has applications in many disciplines and is fun to use. The program's ability to create interactive text lets the reader have an active voice. Super Story Tree is so flexible that its uses are limited only by your imagination."

Electronic Learning

Scholastic Graphics and Sound Booster Packs™

*Dazzling new sights and sounds for Slide Shop,
Super Story Tree and HyperScreen*

- Holidays and Special Events**
Celebrate with festive borders, full-screen graphics, templates, clip art and music. Perfect for designing holiday cards and greetings.
- People and Places (U.S. History)**
Bring our past to life with images of early exploration and settlement, national crises, immigration, human rights struggles, and more.
- Science and Technology**
Use vibrant visuals and sounds to present key discoveries and inventions in areas such as transportation, medicine, media and communications.
- Science Fiction**
Create a sci-fi masterpiece with futuristic sounds and music, plus aliens in imaginative settings--a space rodeo, a robot repair shop, even an intergalactic prom.
- Mystery**
Turn out a murder mystery or horror show featuring haunted houses, foggy nights, creepy monsters, a cagey private eye, and more.
- Adventure**
Produce breathtaking presentations with scenes that make your heart race: cliff dives, erupting volcanos, safaris, and more.
- Everyday People**
Inject a little bit of local color into your presentations. Visit the doctor's office. Eat in the school cafeteria, or just take a stroll and meet the whole town.

Each requires Slide Shop, Super Story Tree or HyperScreen program disk

Melody Shop - A Booster Pack Plus

*Create and edit your own music for all your
multimedia presentations.*

Play your favorite song on the computer—compose your own songs—or edit music clips from your Scholastic multimedia programs. An easy-to-use format enables you to produce your own music to play, print out, or incorporate into multimedia shows, branching stories and interactive presentations.

Please send me the program(s) indicated. I understand that I may examine it (them) for 30 days. If during that time I am not completely satisfied, I may return my order in resaleable condition for a full refund.

Ship To: (Please print)
Name _____
School _____
Address _____
City, State, Zip _____
Bill To: (Bill at school address only)
Name _____
School _____
Address _____
City, State, Zip _____
Signature _____

Slide Shop 5.25" disks 3.5" disks

Apple	Qty	MS-DOS	Qty	Price	Amount
DM87856	—	DM87860	—	\$79.95	—
DM87858	—	DM87862	—	\$79.95	—

Super Story Tree 5.25" disks 3.5" disks

DM87962	—	DM87966	—	\$79.95	—
DM87964	—	DM87968	—	\$79.95	—

HyperScreen 5.25" disks 3.5" disks

DM87986	—			\$99.95	—
DM87988	—			\$99.95	—

Graphics and Sound Booster Packs (5.25" disks only)

1. Holidays & Special Events	DM86570	—	DM86571	—	\$29.95	—
2. People and Places	DM86572	—	DM86573	—	\$29.95	—
3. Science and Technology	DM86574	—	DM86575	—	\$29.95	—
4. Science Fiction	DM87178	—	DM87179	—	\$29.95	—
5. Mystery	DM87180	—	DM87181	—	\$29.95	—
6. Adventure	DM87182	—	DM87183	—	\$29.95	—
7. Everyday People	DM87184	—	DM87185	—	\$29.95	—

Booster Pack Plus Melody Shop 5.25" disks 3.5" disks

DM82968	—	\$34.95	—
DM82969	—	\$34.95	—

Slide Shop, Super Story Tree, HyperScreen and Melody Shop require 128K (Apple) or 256K (MS-DOS) with Color Graphics Card

A small shipping and handling charge will be added.

Total _____

Fill out and mail to:
Scholastic Software
2931 East McCarty Street
P.O. Box 7502
Jefferson City, MO 65102

Or call
800-541-5513
In Missouri 800-392-2179

Scholastic Graphics & Sound

Booster Packs


for HyperScreen, Slide Shop
and Super Story Tree

Description

Extend and enhance the use of your most favourite multi-media software packages with the latest graphics and sound booster packs from Ashton Scholastic. Each pack includes graphic backgrounds, clip-art and sound/musical tunes which are compatible with software titles, including *HyperScreen*, *Super Story Tree* and *Slide Shop*.

Adventure Booster Pack

Enter exciting worlds of adventure and heroism that you only dreamed of before. With this booster pack you can sail your own pirate ship, climb the highest mountain, forage through the jungle and skydive from a plane and come up smiling. Indiana Jones never had this much stamina!




An avalanche, a volcano and a blazing building are just a few of the 24 graphic backgrounds available in this pack, along with 86 pieces of clip-art, grouped under such titles as Wild Animals and Scenery, People in Peril, Adventurers and Rescue Tools. Dramatise your on-screen creations with exciting sound and musical clips (35 included in this pack) and you have created a truly individual adventure.

ASHTON


 SCHOLASTIC

PO Box 579
Gosford NSW 2250 Australia
Telephone: (043) 28 3555
Telex: AA24881
Fax: (043) 28 2205



Everyday People Booster Pack

Take a stroll along the beach, play an invigorating game of soccer or go shopping in a busy mall. All this and more is at your creative finger-tips with the *Everyday People Booster Pack*. The 25 graphic backgrounds, including a doctor's office, a courtroom, a bowling alley and a front porch, provide backdrops for your creativity. Select one or several of the 85 pieces of clip-art to illustrate your setting and add to this an appropriate piece of music, sound or speech from the 34 sound clips designed for this pack.



Regd. Office: Ashton Scholastic Pty Limited (INC. NSW) Railway Crescent Lisarow NSW 2251
Offices also in Adelaide, Brisbane, Melbourne and Perth.

Mystery Booster Pack


Who is that masked man? Can Sherlock Holmes solve the mystery? What lies behind the closet door? Design answers to all these questions and more with the *Mystery Graphics and Sound Booster Pack*. With this pack you will enter an awesome world of bone-chilling suspense and horror. There are clip-art creatures, suspects and clues; graphic backgrounds of an eerie graveyard and a museum. Add to this the sound of footsteps or a creaky door (just two of the 26 sound clips available on this pack) and you have created your own suspense packed scene.

Science Fiction Booster Pack

Utilise the 25 graphic backgrounds, 78 pieces of clip-art and 22 sound and musical clips to build your own sci-fi scene. Start with a roller skating rink around Saturn, adorn it with clip-art aliens and add a bopping alien rock and roll sound clip! Clip-art categories include aliens, animals, earthlings, food, land scenery, robots, toys, vehicles and weirdthings. And of course, included in the repertoire of sound clips is the well known phrase – "Take me to your leader".

Science/Technology Booster Pack

Re-discover dates, inventions and famous scientists with the *Science/Technology Booster Pack*. Set the scene by selecting one of the background graphics relating to the Industrial Revolution and then graphically expand upon your ideas by selecting and positioning relevant inventors, inventions and other graphics from the 78 piece strong library of science and technology clip-art. Graphic backgrounds (35 in all) relate to major inventions, medicine, space, computers, science and mathematics. And with 22 sound and musical clips, what better way is there to integrate the use of multimedia software into the history, science and maths classrooms!



Compatible/Companion Software

- *Slide Shop*
- *Super Story Tree*
- *HyperScreen*
- *Super Print* (with the *Pelican Graphics Converter*)

Contents

Each *Graphics and Sound Booster Pack* contains an illustrated teacher manual which provides a wide variety of cross-curriculum activities, using the classroom multimedia software packages – *Super Story Tree*, *Slide Shop* and *HyperScreen*; plus program disks.

Age

10 – Adult

Adventure Booster Pack

SCS 87182 Apple IIe(128K)/IIc/IIgs\$29.95

SCS 87183 MS-DOS\$29.95

Everyday People Booster Pack

SCS 87184 Apple IIe(128K)/IIc/IIgs\$29.95

SCS 87185 MS-DOS\$29.95

Mystery Booster Pack

SCS 87180 Apple IIe(128K)/IIc/IIgs\$29.95

SCS 87181 MS-DOS\$29.95

Science Fiction Booster Pack


SCS 87178 Apple IIe(128K)/IIc/IIgs\$29.95

SCS 87179 MS-DOS\$29.95


Science/Technology Booster Pack

SCS 86574 Apple IIe(128K)/IIc/IIgs\$29.95

SCS 86575 MS-DOS\$29.95



Melody Shop



PO Box 579
Gosford NSW 2250 Australia
Telephone: (043) 28 3555
Telex: AA24881
Fax: (043) 28 2205

Description


Melody Shop is a simple music program that enables you to compose, transcribe, edit, print and playback music which can be stored on a disk, independently. As an added bonus, it is compatible with the entire range of Scholastic Multimedia Software. You can create new compositions with *Melody Shop*, or edit existing music from *Scholastic Slide Shop*, *Super Story Tree*, *HyperScreen* and the *Scholastic Graphics and Sound Booster Packs*. *Melody Shop* is easy to use. Whatever your musical level, *Melody Shop* allows you to enjoy experimenting with music.

Features and Benefits

- *Melody Shop*'s music notation and play back abilities allow you to create a new tune, edit an existing piece of music, or transcribe a favourite piece of music by ear or from sheet music.
- Choose from 30 key signatures and eight time signatures.
- Experiment with notes and tempos and play back what you have composed or edited while you are creating it.
- **Save your creation on a formatted ProDOS data disk or a self-booting Melody Disk (which do not require the *Melody Shop* program to run).**
- Incorporate your original or transcribed tune into a *Slide Shop* slide show, a *Super Story Tree* story or a *HyperScreen* stack.

Curriculum Ideas

- Set the alphabet to music! Create a auto-running *Slide Shop* presentation using the letters of the alphabet and a single note for each letter (a la the ABC song).
- Select one tune or piece of music. Experiment with beats and tempos to see what effects these have on the mood of the music. Can very familiar pieces of music be made unrecognisable by simply changing the tempo? Experiment and discuss the results with the class.
- In much the same way as you would create a shared story, create a shared musical composition. Break the class up into groups and have them separately work on a piece of music (it may be original or transcribed but it is best if you limit each piece to a set number of bars or beats). Chain the pieces together to form one composition and critically analyse it.



- Write a two-voice melody that incorporates solo and rhythmic accompaniment in both voices. Experiment with the ways in which rests enhance music.

Compatible/Companion Software

- *Slide Shop*
- *Super Story Tree*
- *HyperScreen*
- *Scholastic Graphics and Sound Booster Packs*

Contents

One program disk, back-up facility plus a user guide. The disk contains the *Melody Shop* program of music writing, editing and play back tools, as well as several short pieces of music to play, edit and experiment with.

Age

9 – Adult

Versions

SCS 82968	Apple IIe/IIc (128K)	\$49.95
SCS 82969	Apple 3.5	\$49.95
SCS 82968SL	Apple Site Licence	\$199.95

ASHTON

 SCHOLASTIC

Regd. Office: Ashton Scholastic Pty Limited (INC. NSW) Railway Crescent Lisarow NSW 2251
Offices also in Adelaide, Brisbane, Melbourne and Perth.

**SOFTWARE LICENSE AND LIMITED WARRANTY AGREEMENT FOR
NON-COPY PROTECTED SOFTWARE PUBLISHED BY SCHOLASTIC INC.**

IMPORTANT: READ THIS LICENSE AND LIMITED WARRANTY AGREEMENT CAREFULLY BEFORE USING THE ENCLOSED SOFTWARE AND DOCUMENTATION. THEN, IF YOU AGREE WITH THE TERMS OF THIS AGREEMENT, FILL OUT AND SIGN THE ATTACHED WARRANTY REGISTRATION CARD AND SEND IT TO SCHOLASTIC INC. (SCHOLASTIC). IF YOU DO NOT AGREE WITH THESE TERMS, RETURN THIS PACKAGE TO SCHOLASTIC IN RESALEABLE CONDITION FOR A FULL REFUND.

1. COPYRIGHT

The software programs contained on the disk(s) and the documentation in this package are fully protected by U.S. copyright law. Scholastic and/or the author(s) of this program own all right, title and interest in any copyright in the program. **It is against the law to copy or in any way duplicate the documentation, disk(s), or any portion of the program except under the terms and conditions expressly stated in this Software License and Warranty Agreement.**

2. NON-COPY PROTECTED SOFTWARE

The software programs on the disk(s) in this package are **NOT** copy protected. They are intended for use as Archival disk(s). You **SHOULD** make Legal Copies of the Archival disk(s), but only under the terms described in this Agreement.

Scholastic has provided non-copy protected disks as a matter of convenience for its customers. However, the absence of copy protection in no way diminishes the copyrights of Scholastic and the author(s).

3. USER'S RIGHTS AND RESPONSIBILITIES

Under the terms of this license and U.S. copyright law, you have certain rights to use the disk(s) and documentation included in this package. You also have the responsibility not to use the disk(s) and documentation in a manner that violates this license or copyright laws. Any rights not specifically granted herein are reserved by Scholastic. Your specific rights and responsibilities are:

Previewing the Program

- You **MAY** use and review the software and documentation in this package for up to 30 days before deciding to purchase it. If you do not return the complete package to Scholastic in resaleable condition within that 30 day period, you agree to purchase the software package.
- You **MAY NOT** copy the contents of the disk(s) or any of the documentation in this package for any reasons whatsoever unless and until you have decided to purchase the software.

Completing the Warranty Registration Card

- Once you have purchased the software package, you **MUST** complete the attached Warranty Registration Card and return it to Scholastic to be eligible for technical service, free disk replacement, product information, and free disk updates.

Making and Using Legal Copies

- You **MUST** make one Legal Copy for each Archival disk included in the package. Follow these instructions:
 - Use any standard disk copy program or function to copy the contents of each Archival disk onto one blank disk.
 - On the appropriate Legal Copy label(s) included in your package, enter the serial number that appears on the Warranty Registration Card. Affix this label to the Legal Copy disk(s).
 - Store the Archival disk(s) in a safe place with a copy of this Agreement.
- You **MAY NOT** make more than one Legal Copy of the contents of any disk for use at any one time.
- If you want multiple Legal Copy disks, you **MAY**, as the owner of the program, buy them from Scholastic at a per disk price to create a Customized Lab Pack, or you may buy a site license, which entitles you to make unlimited Legal Copies for use within a defined site.
- You **MAY NOT** make a copy from a Legal Copy disk.
- You **MAY NOT** use the Archival disk(s) for running the program. Use the Legal Copy disk(s) only.
- You **MAY NOT** load the contents of a Legal Copy disk into more than one computer for simultaneous use. This so called "multi-loading" constitutes unauthorized copying and is expressly forbidden by this Agreement.

- You **MAY NOT** copy the program onto a network or other multiple-user device. If you wish to install the program on a network or other multiple-user device, you **MUST** purchase a network version or a network license for the stand-alone version of the program.
- You **MAY** install the program onto and use the program on one hard disk at any one time. To install the program on additional hard disks, you **MUST** purchase additional packages or a site license.

Replacing a Damaged or Defective Legal Copy or Archival Disk

- If a Legal Copy of the program is damaged or defective, first try recopying the program from the Archival disk to the Legal Copy disk. If the program still does not work, the Legal Copy disk medium itself may be defective. In this case, copy the program from the Archival disk to another disk as a temporary Legal Copy. Then send the defective Legal Copy disk to Scholastic for a free replacement. When you receive the replacement, you **MUST** erase the temporary Legal Copy that you made.
- If the Archival disk is damaged or defective, return it to Scholastic for a free replacement (see instructions under Software Warranty and Lifetime Replacement Policy below).

Copying the Documentation

- You **MAY NOT** duplicate pages from the enclosed documentation for any purpose unless permission is expressly granted within the documentation.
- You **MAY NOT** make copies of activity books or any other print items that are sold separately by Scholastic.
- For permission to copy print materials for use at workshops or teacher training sessions, contact Scholastic Software at 800-541-5513. In Missouri, call 800-392-2179.

Restriction on Distribution, Sale or Lease of Programs or Documentation

- You **MAY NOT** distribute, sell or lease copies of the program or documentation unless you have been given explicit written permission to do so by Scholastic.

4. SOFTWARE WARRANTY AND LIFETIME REPLACEMENT POLICY

Scholastic warrants the original purchaser of this product that the disk(s) containing the Scholastic program shall be free from defects in materials and workmanship. If a disk becomes defective at any time, you may return it to Scholastic for a free replacement. To be eligible for free disk replacements and technical support, you **MUST HAVE** completed and returned the attached Warranty Registration Card.

Send disk(s) and
correspondence to:

Scholastic Software
P.O. Box 7502
2391 E. McCarty St.
Jefferson City, MO 65102

In Canada:

Scholastic Software
123 Newkirk Rd.
Richmond Hill L4C 3G5
Ontario, Canada

5. DISCLAIMER

This warranty does not apply to the software programs contained on Scholastic disks, which programs are sold "as is". This warranty is in lieu of all other warranties, whether oral or written, expressed or implied. Any implied warranties, including implied warranties of merchantability and fitness for a particular purpose, are limited in duration to ninety (90) days from the date of purchase of this product. Scholastic shall not be liable for incidental and/or consequential damages for the breach of any expressed or implied warranty, including damage to property and, to the extent permitted by law, damages for personal injury. Some states do not allow the exclusion or limitations on how long an implied warrant lasts, so the above limitation or exclusion may not apply to you.

This warranty shall not be applicable to the extent that any provision is prohibited by any federal, state, or municipal law that cannot be preempted. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

6. MISCELLANEOUS

This Software License shall be governed by the laws of the State of New York and shall inure to the benefit of Scholastic Software, a division of Scholastic Inc., its successors and assigns.

7. ACKNOWLEDGEMENT

Licensee acknowledges that he has read this Software License, understands it, and agrees to be bound by its terms and conditions. Licensee also agrees that this agreement is the complete and exclusive statement of agreement between the parties and supersedes all proposals or prior agreements, verbal or written, and any other communications between the parties relating to the subject matter of this agreement.

SERIAL NO.: 102649

DETACH WARRANTY REGISTRATION CARD HERE

SEAL WITH TAPE HERE

SERIAL NO.: 102649

11. What source(s) of funds were used to purchase this product?
☐ District Budget
☐ School Budget
☐ Federal Funds
☐ State Funds
Other (Specify): _____

10. For each of the following questions, enter the code that corresponds to the appropriate answer.
01- Teacher
02- Principal
03- Department Head
04- Computer Coordinator
a) Who expressed initial interest in buying this product? Code _____
b) Who made the final decision to purchase this product? Code _____
c) Who placed the order for this product? Code _____

9. How is the product primarily used?
☐ Basic Instruction
☐ Enrichment
☐ Remediation
☐ Tool

8. Where is product primarily used?
☐ Classroom
☐ Computer Lab
☐ Library/Media Center
☐ Resource Room
☐ Office
Other (Specify): _____

7. Which subject(s) use this product?
☐ Math
☐ Science
☐ Reading
☐ Language Arts
☐ Business Ed
☐ Social Studies
☐ Computer Studies
Other (Specify): _____

▼ FOLD ALONG THIS LINE ▼



NO POSTAGE
NECESSARY
IF MAILED
IN THE
UNITED STATES

BUSINESS REPLY MAIL

First Class Permit No. 9411 New York, NY

POSTAGE WILL BE PAID BY ADDRESSEE

SCHOLASTIC SOFTWARE®

Scholastic
730 Broadway
New York, NY 10003

▼ DETACH WARRANTY REGISTRATION CARD HERE ▼

Attn: Marketing Dept.

SCHOLASTIC SOFTWARE WARRANTY REGISTRATION CARD

To be eligible for technical service, free disk replacement, product information, and free disk updates, please complete the following.

Name: _____

I have read the Software License and Warranty Agreement and agree to abide by its terms.

Signature _____ Date _____

Title:

<input type="checkbox"/> Teacher	<input type="checkbox"/> Curriculum Coordinator
<input type="checkbox"/> Department Head	<input type="checkbox"/> Other (Specify): _____
<input type="checkbox"/> Computer Coordinator	

(If non-teacher, please fill in home address)

School _____

Street Address

City, State, Zip _____

Title of Product Purchased _____

Date Purchased _____

Ages of Software User(s): (circle all that apply)

6	7	8	9	10	11	12	13	14	15	16	17	18	Adult
---	---	---	---	----	----	----	----	----	----	----	----	----	-------

Computer Version: ☐ Apple ☐ MS-DOS

Disk Format: ☐ 5.25" ☐ 3.5"

1. How did you learn about this product?

<input type="checkbox"/> Scholastic Software Catalog	<input type="checkbox"/> Magazine Review
<input type="checkbox"/> Scholastic Sales Representative	<input type="checkbox"/> Educators' Workshop
<input type="checkbox"/> Scholastic Authorized Education Dealer	<input type="checkbox"/> Scholastic Family Catalog
<input type="checkbox"/> Received Information in the Mail	<input type="checkbox"/> Recommended by friend/colleague
<input type="checkbox"/> Magazine Advertisement	

- 2. What factor most influenced your decision to purchase this product?**

(Please check one box only.)

<input type="checkbox"/> Scholastic's reputation	<input type="checkbox"/> Service/Warranty Policy
<input type="checkbox"/> Price	<input type="checkbox"/> Other (Specify): _____
<input type="checkbox"/> Wanted that specific product	

(Educators only please continue)

3. **School Location:** ☐ Urban ☐ Suburban ☐ Rural
School Type: ☐ Public ☐ Private
Student Enrollment: ☐ 1-299 ☐ 300-499 ☐ 500+

4. Approximate number of the following computers in your school:

Apple II Series IBM/MS-DOS Macintosh

5. Memory most available: ☐ 48K ☐ 128K ☐ 512K
☐ 64K ☐ 256K ☐ 1MB

- 6. Disk drive configuration most available:**

☐ One 5.25" ☐ Two 3.5" ☐ One 5.25" and one 3.5"

☐ Network ☐ Hard Disk

- continued -

ASHTON SCHOLASTIC PTY LIMITED

COMPUTER PROGRAM LICENCE TERMS AND CONDITIONS

1. Licence

In consideration of the payment by you of a once only licence fee the receipt of which is hereby acknowledged, Ashton Scholastic Pty Limited (Ashton Scholastic) hereby grants to you a non-transferable non-exclusive licence to use the computer program recorded on the diskette(s) herein ("the Computer Program") on one central processing unit at one location subject always to the terms and conditions herein.

2. Network Licences

The Computer Program may not be networked. You undertake to enter into an additional licence on terms and conditions as may be agreed and pay the relevant additional licence fee assessed by Ashton Scholastic in respect of any networking proposed by you of the Computer Program.

3. Copyright and Other Intangible Property Rights

The copyright and all other intangible property rights in the Computer Program are reserved and vest in Ashton Scholastic. The Computer Program may not be reproduced or copied in whole or in part by any means or process whatsoever whether for the purpose of making a back-up copy or for any other purpose whatsoever, without prior written consent of Ashton Scholastic.

4. Your Responsibilities

You covenant that your employees and agents shall comply and adhere to the provisions of this Agreement.

5. Warranties

- (a) Subject to your completion and return of the Warranty Registration Card to Ashton Scholastic, Ashton Scholastic warrants to you that the diskette(s) supplied in respect of the Computer Program shall be free of defects in respect of workmanship and materials for a period of sixty (60) days from the date of purchase. Under this warranty Ashton Scholastic shall replace any defective diskette(s) if a claim is made by you pursuant to Clause 5(b) hereof and the said diskette(s) is/are proven to Ashton Scholastic's satisfaction to be defective. If the said diskette(s) is/are so defective and a claim is made by you pursuant to Clause 5(b) hereof within three (3) years after the said sixty (60) day period, Ashton Scholastic shall replace the said diskette(s) following payment by you to Ashton Scholastic of \$10.00.

The above warranties do not apply to any diskette which has been modified or subject to abuse, misuse, abnormal stress or strain, or neglect of any kind.

Warranties Continued

- (b) Defective diskette(s) shall be returned in its/their original diskette jacket(s) placed between two sheets of firm cardboard, then placed in an outer envelope marked "FRAGILE — DO NOT BEND", and sent together with proof of purchase, a written statement describing the defect, a cheque for \$10.00 (only if the claim is not made within the said sixty (60) day period), and your return address and telephone number.
- (c) Subject to the Trade Practices Act (Cth) 1974 (as amended), applicable state legislation and Clause 5(a) hereof all other warranties and liability implied or expressed by statute or common law whether in relation to the Computer Program or the diskette(s) are hereby expressly excluded. Ashton Scholastic's liability herein shall in all circumstances be limited to the replacement cost of any defective diskette(s) and it is agreed and declared that Ashton Scholastic shall under no circumstances be liable for any direct or indirect loss or damage of any kind whatsoever suffered by you or any other party, whether as a consequence of the breach of any term or condition herein or as a consequence of negligence or otherwise.

6. Termination

Ashton Scholastic may by notice in writing to you terminate the licence herein granted forthwith following your breach of any term

or condition hereof. Upon termination of the licence herein granted for any reason whatsoever you shall forthwith destroy all diskettes and media reproducing the same in material form.

7. General

- (a) For the purposes of this Agreement "diskette" means a floppy disk and its protective jacket and does not include the Computer Program.
- (b) There are no conditions or warranties or other terms affecting the arrangement between you and Ashton Scholastic other than those embodied herein and this Agreement contains the whole of the contract between the parties.
- (c) The proper law of this Agreement shall be the law of New South Wales and the Commonwealth of Australia as applicable.

Address all correspondence to:

Ashton Scholastic
PO Box 579
Gosford NSW 2250

Phone enquiries:
Sydney (02) 922 6777
Head Office: (043) 28 3555
Melbourne: (03) 889 3667
Brisbane: (07) 831 8555
Adelaide: (08) 223 7563
Perth: (09) 321 1344

WARRANTY REGISTRATION CARD

Person Registering Product: _____

Name of School/Purchaser: _____

School/Private Address: _____

Postcode: _____

Date of Purchase: _____ (Home/School Use)

Product Purchased: _____

Primary Use of Computer Program: ☐ School ☐ Home ☐ Office ☐ Other

Age Level(s) Using Product: _____ Name/Type of Computer: _____


How did you learn about your product purchase?

_____ MAGAZINE ADVERTISEMENT	_____ MAILING BROCHURE
_____ SOFTWARE SUPPLIER	_____ COMPUTER DEALER
_____ ASHTON SCHOLASTIC CONSULTANT	_____ SOFTWARE CATALOGUE
_____ WORD OF MOUTH	_____ INSERVICE/TRAINING COURSE
_____ OTHER, PLEASE SPECIFY _____	

You acknowledge that you have read the Computer Program Licence: Terms and Conditions, understand them and agree to be bound by them:

Signature of Person Duly Authorised to sign
this Warranty Registration Card: _____ Date: _____

No postage stamp required
if posted in Australia



ASHTON SCHOLASTIC
P.O. BOX 579,
GOSFORD, N.S.W. 2250